Windows PowerShell | Windows PowerShell

```
PS C:\GDB_tutorial\largest_s> make
Assembling
C:/altera_pro/26.1/fpgacademy/AMP/cygwin64/home/compiler/bin/riscv32-unknown-elf-as.exe -march=rv32im_zicsr --gdwarf2 la
rgest.s -o largest.s.o
Linking
C:/altera_pro/26.1/fpgacademy/AMP/cygwin64/home/compiler/bin/riscv32-unknown-elf-ld.exe --section-start .text=0x0 --no-r
elax largest.s.o -o largest.elf

PS C:\GDB_tutorial\largest_s> cd ..\display_C\
PS C:\GDB_tutorial\display_C> make
Compiling
C:/altera_pro/26.1/fpgacademy/AMP/cygwin64/home/compiler/bin/riscv32-unknown-elf-gcc.exe -Wall -c -g -O1 -ffunction-sect
ions -fverbose-asm -fno-inline -gdwarf-2  -march=rv32im_zicsr -mabi=ilp32 display.c -o display.c.o
Linking
C:/altera_pro/26.1/fpgacademy/AMP/cygwin64/home/compiler/bin/riscv32-unknown-elf-gcc.exe-Wl,--defsym=__stack_pointer$=0x
4000000 -Wl,--defsym  -Wl,JTAG_UART_BASE=0xff201000 -lm -march=rv32im_zicsr -mabi=ilp32 display.c.o -o display.elf

PS C:\GDB_tutorial\display_C> make gdb_client
riscv32-unknown-elf-gdb.exe -silent -ex "target remote:2454" -iex "set $mstatus=0" -iex "set $mtvec=0" -iex "set $pc=_st
art" -ex "load" -ex "info reg pc" "display.elf"
No symbol table is loaded.  Use the "file" command.
Reading symbols from display.elf...
Remote debugging using :2454
0x00000000 in ?? ()
Loading section .text, size 0x1f44 lma 0x10094
Loading section .eh_frame, size 0x4 lma 0x12000
Loading section .init_array, size 0x4 lma 0x12004
Loading section .fini_array, size 0x4 lma 0x12008
Loading section .data, size 0x548 lma 0x12010
Loading section .sdata, size 0x14 lma 0x12558
Start address 0x00010094, load size 9388
Transfer rate: 79 KB/sec, 1564 bytes/write.
pc             0x10094  0x10094 <_start>
(gdb)
```