We use optional cookies to improve your experience on our websites, such as through social media connections, and to display personalized advertising based on your online activity. If you reject optional cookies, only cookies necessary to provide you the services will be used. You may change your selection by clicking "Manage Cookies" at the bottom of the page. Privacy Statement Third-Party Cookies

Accept

Reject

Manage cookies

# Microsoft Ignite

Nov 19-22, 2024

Register now >



Learn

Product documentation ∨ Development languages ∨

Q Sign in

**Windows Server** 

Get started Failover clustering Management Identity and access Networking Troubleshooting

Related products ~

🔽 Filter by title

#### sysochigi systeminfo

takeown

tapicfg

taskkill

tasklist

tcmsetup

> telnet

tftp time

timeout

title

tlntadmn

tpmtool

tpmvscmgr

tracerpt tracert

tree

tsdiscon

tsecimp

tskill

tsprof type

typeperf

tzutil

unlodctr

ver

verifier

verify

vol

> vssadmin

waitfor

> wbadmin

> wdsutil

Learn / Windows Server /

# systeminfo

Article • 02/03/2023 • 7 contributors •

Applies Windows Server 2025, Windows Server 2022, Windows Server 2019, Windows

Server 2016, ✓ Windows 11, ✓ Windows 10, ✓ Azure Stack HCI, versions 23H2 and 22H2

් Feedback

#### In this article

**Syntax** 

**Examples** 

Related links

Displays detailed configuration information about a computer and its operating system, including operating system configuration, security information, product ID, and hardware properties (such as RAM, disk space, and network cards).

### **Syntax**

1 Copy systeminfo [/s <computer> [/u <domain>\<username> [/p <password>]]] [/fo {TABLE

#### **Parameters**

Expand table

| Parameter                                   | Description  |
|---|--|
| /S <computer></computer>                    | Specifies the name or IP address of a remote computer (do not use backslashes). The default is the local computer.   |
| /u <domain>\ <username></username></domain> | Runs the command with the account permissions of the specified user account. If /u is not specified, this command uses the permissions of the user who is currently logged on to the computer that is issuing the command. |
| /p <password></password>                    | Specifies the password of the user account that is specified in the /u parameter.  |

Download PDF

| /fo <format></format> | <ul> <li>Specifies the output format with one of the following values:</li> <li>TABLE - Displays output in a table.</li> <li>LIST - Displays output in a list.</li> <li>CSV - Displays output in comma-separated values (.csv) format.</li> </ul> |
|-----------------------|---|
| /nh                   | Suppresses column headers in the output. Valid when the <b>/fo</b> parameter is set to TABLE or CSV.  |
| /?                    | Displays help at the command prompt.  |

# **Examples**

To view configuration information for a computer named *Srvmain*, type:



To remotely view configuration information for a computer named *Srvmain2* that is located on the *Maindom* domain, type:

```
Systeminfo /s srvmain2 /u maindom\hiropln
```

To remotely view configuration information (in list format) for a computer named *Srvmain2* that is located on the *Maindom* domain, type:



### **Related links**

• Command-Line Syntax Key

### **Feedback**

© English (United States) ✓× Your Privacy Choices 

† Theme ✓

Manage cookies Previous Versions Blog ☑ Contribute Privacy ☑ Terms of Use Trademarks ☑ © Microsoft 2024