We use optional cookies to improve your experience on our websites, such as through social media connections, and to display personalized advertising based on your online activity. If you reject optional cookies, only cookies necessary to provide you the services will be used. You may change your selection by clicking "Manage Cookies" at the bottom of the page. **Privacy Statement Third-Party Cookies**

Accept

Reject

Manage cookies



Learn

Discover \

Product documentation ∨

Development languages ~

Topics ∨

Q Sign in

(+)



Install Hyper-V on Windows

Article • 08/12/2024 • 13 contributors

্ৰ Feedback

In this article

Check requirements

Enable Hyper-V using PowerShell

Enable Hyper-V with CMD and DISM

Enable the Hyper-V role through Settings

Make virtual machines

Enable Hyper-V to create virtual machines on Windows. Hyper-V can be enabled in many ways including using the Windows control panel, PowerShell or using the Deployment Imaging Servicing and Management tool (DISM). This document walks through each option.

① Note

Hyper-V is built into Windows as an optional feature -- there's no Hyper-V download.

Check requirements

- Windows 10 (Pro or Enterprise), or Windows 11 (Pro or Enterprise)
- 64-bit Processor with Second Level Address Translation (SLAT).
- CPU support for VM Monitor Mode Extension (VT-c on Intel CPUs).
- Minimum of 4 GB memory.

① Note

The Hyper-V role **can't** be installed on Windows 10 Home or Windows 11 Home.

For more information and troubleshooting, see Windows Hyper-V System Requirements.

Enable Hyper-V using PowerShell

- 1. Open a PowerShell console as Administrator.
- 2. Run the following command:

Enable-WindowsOptionalFeature -Online -FeatureName Microsoft

If the command isn't found, make sure you're running PowerShell as Administrator.

1. When the installation completes, reboot.

Enable Hyper-V with CMD and DISM

The Deployment Image Servicing and Management tool (DISM) helps configure Windows and Windows images. Among its many applications, DISM can enable Windows features while the operating system is running.

To enable the Hyper-V role using DISM:


- 1. Open up a PowerShell or CMD session as Administrator.
- 2. Type the following command:

DISM /Online /Enable-Feature /All /FeatureName:Microsoft-Hyr

For more information about DISM, see the DISM Technical Reference.

Enable the Hyper-V role through Settings

- 1. Navigate to the Control Panel.
- 2. Select **Programs**, then **Programs and Features**.
- 3. Select Turn Windows Features on or off.
- 4. Select **Hyper-V** and then select **OK**.



When the installation completes you're prompted to restart your computer.

Make virtual machines

Create your first virtual machine

Feedback

