

DHCP


franz-bonaparta.github.io


DHCP


DHCP to usługa sieciowa, która automatycznie i dynamicznie przydziela konfigurację IP (adres IP, maskę podsieci, bramę domyślną, serwery DNS) urządzeniom w sieci lokalnej. Dzięki temu administrator nie musi ręcznie konfigurować każdej stacji roboczej, co zapobiega konfliktom adresów IP. Usługa ta działa w architekturze klient-serwer i opiera się na procesie DORA (Discover, Offer, Request, Acknowledge) na portach UDP 67 i 68.


KONFIGURACJA DHCP

TREŚĆ ZADANIA: ZAINSTALUJ ROLĘ SERWERA DHCP. SKONFIGURUJ ZAKRES (SCOPE) O NAZWIE LAN-DHCP DLA SIECI WEWNĘTRZNEJ. ZAKRES MA PRZYDZIELAĆ ADRESY OD 192.168.0.50 DO 192.168.0.100. USTAW BRAMĘ DOMYŚLNĄ NA 192.168.0.1 ORAZ CZAS DZIERŻAWY NA 2 DNI.









FileEditViewVMTabsHelp

HomeWindows Server 2016 (2)

Server Manager

Server Manager Dashboard

DashboardLocal ServerAll ServersFile and Storage

WELCOME TO SERVER MANAGER

Add Roles and Features Wizard

Select destination server

DESTINATION SERVER
WIN-1H59Q3VPLQU

Before You Begin
Installation Type
Server Selection
Server Roles
Features
Confirmation
Results

Select a server or a virtual hard disk on which to install roles and features.
☒ Select a server from the server pool
☐ Select a virtual hard disk

Server Pool

Filter:

Name	IP Address	Operating System
WIN-1H59Q3VPLQU	192.168.89.129	Microsoft Windows Server 2016 Standard Evaluation

1 Computer(s) found
This page shows servers that are running Windows Server 2012 or a newer release of Windows Server, and that have been added by using the Add Servers command in Server Manager. Offline servers and newly-added servers from which data collection is still incomplete are not shown.

< PreviousNext >InstallCancel

1


6/14/2026 2:47 PM6/14/2026 2:47 PM


Windows Server 2016 (2) - VMware Workstation

23:53
6/14/2026

To direct input to this VM, move the mouse pointer inside or press Ctrl+G.

23:53
14/06/2026








Windows Server 2016 (2) X



Recycle Bin




Windows Server 2016 Standard Evaluation
Windows License valid for 180 days
Build 14393.rs1_release.161220-1747

To direct input to this VM, move the mouse pointer inside or press Ctrl+G.



5:40 PM
6/14/2026

ENG
UK
02:40
15/06/2026



win-1h59q3vplqu

- IPv4
 - Display Statistics...
 - New Scope...
 - New Multicast Scope...
 - Configure Failover...
 - Replicate Failover Scopes...
 - Define User Classes...
 - Define Vendor Classes...
 - Reconcile All Scopes...
 - Set Predefined Options...
 - View
 - Refresh
 - Properties
 - Help



Add a Scope

A scope is a range of IP addresses assigned to computers requesting a dynamic IP address. You must create and configure a scope before dynamic IP addresses can be assigned.

To add a new scope, on the Action menu, click New Scope.

For more information about setting up a DHCP server, see online Help.

Actions

IPv4

More Actions

Add a Scope

A scope is a range of IP addresses assigned to computers requesting a dynamic IP address. You must create and configure a scope before dynamic IP addresses can be assigned.

To add a new scope, on the Action menu, click New Scope.

For more information about setting up a DHCP server, see online Help.

New Scope Wizard



Welcome to the New Scope Wizard

This wizard helps you set up a scope for distributing IP addresses to computers on your network.


To continue, click Next.



[< Back](#)

[Next >](#)

Cancel





Add a Scope

A scope is a range of IP addresses assigned to computers requesting a dynamic IP address. You must create and configure a scope before dynamic IP addresses can be assigned.

To add a new scope, on the Action menu, click New Scope.

For more information about setting up a DHCP server, see online Help.

New Scope Wizard

IP Address Range

You define the scope address range by identifying a set of consecutive IP addresses.



Configuration settings for DHCP Server -

Enter the range of addresses that the scope distributes.

Start IP address: 192 . 168 . 0 . 50

End IP address: 192 . 168 . 0 . 100

☐ Configuration settings that propagate to DHCP Client


Length:

Subnet mask: 255 . 255 . 255 . 0

[< Back](#)

[Next >](#)

Cancel





Add a Scope

A scope is a range of IP addresses assigned to computers requesting a dynamic IP address. You must create and configure a scope before dynamic IP addresses can be assigned.

To add a new scope, on the Action menu, click New Scope.

For more information about setting up a DHCP server, see online Help.

New Scope Wizard

Lease Duration

The lease duration specifies how long a client can use an IP address from this scope.

Lease durations should typically be equal to the average time the computer is connected to the same physical network. For mobile networks that consist mainly of portable computers or dial-up clients, shorter lease durations can be useful. Likewise, for a stable network that consists mainly of desktop computers at fixed locations, longer lease durations are more appropriate.

Set the duration for scope leases when distributed by this server.

Limited to:

Days:

2

Hours:

0


Minutes:



[< Back](#)

[Next >](#)

Cancel





Add a Scope

A scope is a range of IP addresses assigned to computers requesting a dynamic IP address. You must create and configure a scope before dynamic IP addresses can be assigned.

To add a new scope, on the Action menu, click New Scope.

For more information about setting up a DHCP server, see online Help.

New Scope Wizard

Router (Default Gateway)

You can specify the routers, or default gateways, to be distributed by this scope.

To add an IP address for a router used by clients, enter the address below.

IP address:

192 . 168 . 0 . 1

Add

Remove

Up

Down

[< Back](#)

[Next >](#)

Cancel

**Add a Scope**

A scope is a range of IP addresses assigned to computers requesting a dynamic IP address. You must create and configure a scope before dynamic IP addresses can be assigned.

To add a new scope, on the Action menu, click New Scope.

For more information about setting up a DHCP server, see online Help.

New Scope Wizard**Domain Name and DNS Servers**

The Domain Name System (DNS) maps and translates domain names used by clients on your network.



You can specify the parent domain you want the client computers on your network to use for DNS name resolution.

Parent domain:

To configure scope clients to use DNS servers on your network, enter the IP addresses for those servers.

Server name:

Resolve

IP address:

192.168.89.2

Add

Remove

Up

Down

< Back

Next >

Cancel

Actions

IPv4

More Actions



Add a Scope

A scope is a range of IP addresses assigned to computers requesting a dynamic IP address. You must create and configure a scope before dynamic IP addresses can be assigned.

To add a new scope, on the Action menu, click New Scope.

For more information about setting up a DHCP server, see online Help.

New Scope Wizard

WINS Servers

Computers running Windows can use WINS servers to convert NetBIOS computer names to IP addresses.

Entering server IP addresses here enables Windows clients to query WINS before they use broadcasts to register and resolve NetBIOS names.

Server name:

Resolve

IP address:

Add

Remove

Down

To change this behavior for Windows DHCP clients modify option 046, WINS/NBT Node Type, in Scope Options.

[< Back](#)

[Next >](#)

Cancel



Add a Scope

A scope is a range of IP addresses assigned to computers requesting a dynamic IP address. You must create and configure a scope before dynamic IP addresses can be assigned.

To add a new scope, on the Action menu, click New Scope.

For more information about setting up a DHCP server, see online Help.

New Scope Wizard

Activate Scope

Clients can obtain address leases only if a scope is activated.

Do you want to activate this scope now?


☒ Yes, I want to activate this scope now

☐ No, I will activate this scope later

[< Back](#)

[Next >](#)

Cancel



franz bonaparte