



FULCRUM SUITE

Official overlay guide • functions • configuration

A SimHub / iRacing overlay suite focused on awareness, timing, pit workflows, strategy, environmental data and DigiFlags.



Public baseline documented: Fulcrum Plugin v4.1.32


1. Suite overview

Overlay	Main purpose	Suite control
Delta	Live lap delta, speed delta and timing reference	Global reference
Sectors Pop-Up	Completed-sector pop-up	Global reference
Sectors Table	Recent-sector table	Global reference
Relatives	Drivers, gaps, status, tires and multiclass context	Sliders / toggles
Radar	Nearby-car awareness	Sports / Formula
Rejoin Assistant	Traffic warning during rejoins	Automatic
Pit Assistant	Pit speed, limiter, services and pit time	Automatic
Strategy Engineer	Fuel and stint strategy	Automatic
Systems	Brake bias and vehicle systems	Vehicle dependent
Conditions	Track temperature and conditions	Automatic
Wind	Wind direction and speed	Automatic
DigiFlags	LED panels, flags and alerts	Size / position / brightness

The shared timing reference affects Delta, Sectors Pop-Up and Sectors Table.


2. Timing overlays

Fulcrum Delta v0.8.6.1
Live delta with selectable reference, class-aware logic and smoothed speed delta.



- Can compare against MY BEST LAP or CLASS SESSION BEST.
- The same reference is shared with both Sectors overlays.

Fulcrum Sectors Pop-Up v0.3.2
Appears after completing a sector and shows the captured split.



Fulcrum Sectors Table v0.5.4
Persistent recent-sector table; uses the same shared plugin capture.



Reference	Effect
MY BEST LAP	Delta and Sectors compare against your own best valid lap.
CLASS SESSION BEST	Delta and Sectors compare against the fastest valid lap in your class.

3. Awareness & multiclass racing

Fulcrum Relatives v6.6.88

Shows position, change, car number, driver, license/SR/IR, tire, GAP and last lap.

SOF 2891			INC 1 / 17			TRACK 30.4°C		
POS	+/-	#	DRIVER	LIC / SR / IR	TIRE	GAP	LAST LAP	
2	+1	2	Kyle Loh	A 4.67 / 5.3k	13.0	L15	1:09.506	
3	+2	4	Gavven Scalise	A 1.58 / 4.2k	6.9	L15	1:09.734	
4	-2	3	Landon Loy	B 1.41 / 4.3k	3.3	L15	1:09.602	
5	+1	5	Benjamin Zillins	B 3.25 / 3.5k	1.1	L15	1:10.727	
6	+1	4	Eduardo Escotto	A 3.36 / 3.3k	—	L15	1:10.289	
7	-3	7	Santiago Juarez	A 3.39 / 3.3k	-6.2	L15	1:11.161	
8	+2	6	Marshall Skare	A 2.93 / 2.9k	-7.3	L15	1:11.759	
9	0	12	Kaleb Krail	B 3.21 / 2.1k	-10.7	L15	1:11.254	
10	-2	9	Dylan Ye	A 4.43 / 2.4k	-11.2	L15	1:10.388	
RACE			15 DRIVERS	LAP 15 / 17		02:35 REMAINING		

- The header remains GAP; Direct EST is used underneath.
- Supports configurable rows, sizing, columns, widths and multiple toggles.

Fulcrum Radar v0.6.21

Green self-car silhouette, nearby-car awareness and Sports / Formula modes.



Fulcrum Rejoin Assistant v0.1.12

Shows car count and SAFE / CAUTION / HOLD guidance during a rejoin.

REJOIN

2 CARS · 3.1s


HOLD

4. Strategy, pit work, systems & environment


Fulcrum Strategy Engineer v4.1.1
Fuel and stint planning with tank, plan, average, last and target information.



Fulcrum Pit Assistant v0.1.31
Pit speed, pit limit, limiter status, pit time, fuel, tires, fast repair and repairs.




Fulcrum Systems v0.3.0
Brake bias and supported vehicle systems with the unified Fulcrum visual style.



Fulcrum Conditions v0.4.18
Track temp, air temp and track condition state.



Fulcrum Wind v0.1.11
Wind speed and direction; headwind, tailwind or crosswind.



5. DigiFlags

Current Fulcrum DigiFlags states, effects and controls.

FULCRUM DIGIFLAGS · STATES & EFFECTS

ALL CURRENT FLAG STATES AND CUSTOM ALERT EFFECTS ON A SINGLE PAGE

GREEN FLAG STATE  	ONE LAP TO GREEN RESTART PREP  	YELLOW FLAG STATE  
BLUE FAST CAR APPROACHING  	WHITE FINAL LAP  	RED 2X / 4X INCIDENT  
CHECKERED SESSION FINISH  	BLACK PENALTY FLAG  	MEATBALL MANDATORY REPAIRS  
DEBRIS RED + YELLOW HAZARD  	FLASHER TRIPLE WHITE FLASH  	PIT LIMITER STEADY CYAN  

ENGAGE LIMITER WARNING SEQUENCE
AMBER → CYAN → AMBER → OFF (SLOWER WARNING CADENCE)

1

2

3

4


SUITE-ADJUSTABLE CONTROLS

- PANEL WIDTH
- PANEL HEIGHT
- PANEL GAP / SEPARATION
- HORIZONTAL OFFSET
- VERTICAL OFFSET

6. Plugin installation


1. Close SimHub completely.

Copy Fulcrum.Plugin.dll and Fulcrum.Core.dll into the main SimHub folder. The typical installation path is:




2. Open SimHub and verify the plugin.

Open Add/remove features. Confirm that Fulcrum Suite is enabled and turn on Show in left main menu for direct access.




3. Confirm Fulcrum Suite appears in the left menu.



If it does not appear, return to Add/remove features and check the Show in left main menu toggle.


7. Import the overlays

Open each .simhubdash file from the Overlays folder. SimHub will show the import window; click Import into SimHub library.



Verification


After importing, open Dash Studio > Overlays. Your Fulcrum overlays will appear in the library.



Note: You can import the full Suite or only the overlays you want to use.

8. First setup

Open Fulcrum Suite from the left menu. Changes are saved automatically.



Timing reference

Choose MY BEST LAP or CLASS SESSION BEST. This option affects exactly Delta, Sectors Pop-Up and Sectors Table; Relative GAP is unchanged.

TIMING REFERENCE · DELTA + SECTORS

Choose the lap used as the comparison reference. This setting affects Fulcrum Delta and both Sectors overlays; Relative GAP is unchanged.

- ☒ MY BEST LAP · fastest personal lap in the current session
- ☐ CLASS SESSION BEST · fastest lap set by a driver in your class

MY BEST uses iRacing's native LapDeltaToBestLap. CLASS SESSION BEST uses Fulcrum's validated same-class reference trace. Sector deltas automatically follow the same selection.

9. Fulcrum Suite customization

DigiFlags

You can enable the panels, preview them while configuring, and adjust spacing, width, height, offsets, brightness, incident alert hold and auto-hide.

DIGIFLAGS - LIVE PANEL CORE
Two coordinated octagonal LED panels on a 3440-wide canvas. Spacing is center-based and supports ultrawide virtual mirrors.

☒ Enable DigiFlags

☐ Preview panels while configuring

Panel spacing

2660 px

Panel width

106 px

Panel height

460 px

Horizontal offset

10 px

Vertical offset

-5 px

Brightness

100%

Incident alert hold

2.50 s

☒ Auto-hide with no active signal

Relatives

Each column can be enabled or disabled and its width can be adjusted from the Suite.

COLUMNS
Enable each column and set the space reserved for it. Hidden columns collapse completely.

☒ Position

36 px

☒ Position gain / loss

44 px

☒ Car number

44 px

☒ Country flags

40 px

☒ Driver

266 px

☒ Manufacturer logo

58 px

☒ License + Safety Rating + iRating

192 px

☒ Tire compound

48 px

☒ Overtake / Push-to-Pass

64 px

☒ Live gap

92 px

☒ Status / stint

90 px

☒ Last lap

134 px

10. Support FulcrumTTV



Support FulcrumTTV

Follow the project and upcoming racing content:

YouTube • Twitch • TikTok • Instagram

@FulcrumTTV

If you enjoy Fulcrum Suite and want to support the project, follow FulcrumTTV on:

YouTube	youtube.com/@fulcrumttv
Twitch	twitch.tv/fulcrumttv
TikTok	tiktok.com/@fulcrumttv
Instagram	instagram.com/fulcrumttv

Thank you for supporting the Fulcrum Suite project.