

1. Log in to your home Wi-Fi router's admin panel using its default IP address (usually 192.168.0.1 or 192.168.1.1) and take a screenshot of the login page. If you don't know your router's IP, open Command Prompt and run 'ipconfig' — look for 'Default Gateway'.

Ans.

TP-Link Wireless N Router WR840N

Not secure 192.168.1.1

tp-link TP-Link Wireless N Router Model No. TL-WR840N

Router IP Address (Default Gateway)

Log In with Local Password

Username

Password

Log In

[Forgot Password?](#)

Enter Router Username

Enter Router Password

Default Login Credentials (Example)

Username	Password
admin	admin

Note:
Username and password may vary depending on your router manufacturer or ISP.

2.Find and note down the current IP address, subnet mask, and default gateway assigned to your laptop or mobile device when connected to your Wi-Fi network.

Ans.

Network Detail Value

IP Address 192.168.1.10

Subnet Mask 255.255.255.0

Default Gateway 192.168.1.1




3.Change your device's IP address from 'Obtain IP automatically' (DHCP) to a static IP in the same range as your router (for example, set it to 192.168.1.50 if your router is 192.168.1.1), and test if you still have internet access. Constraint Remember to revert to automatic/DHCP after testing to avoid network issues.

Ans. Steps to Change IP Address to Static

- 1. Connect your laptop to your Wi-Fi.**
- 2. Open Settings → Network & Internet → Wi-Fi.**
- 3. Select your connected Wi-Fi network and open IP settings.**
- 4. Change Automatic (DHCP) to Manual.**
- 5. Turn on IPv4.**
- 6. Enter the following example details:**
 - IP address: 192.168.1.50**
 - Subnet mask: 255.255.255.0**
 - Gateway: 192.168.1.1**
 - DNS: 8.8.8.8**
- 7. Click Save.**
- 8. Open a web browser and visit a website to check whether the internet is working.**

9. After testing, go back to IP settings and change it from Manual back to Automatic (DHCP).

10. Save the settings and reconnect to Wi-Fi.



4. In your router's admin panel, locate the section where you can view or change the DHCP range. Write down the current range, and explain in 2-3 lines what would happen if two devices are assigned the same IP address in this range.

Ans. DHCP Range

First, log in to your router's admin panel and open the DHCP settings. Look for DHCP Server, DHCP Range, or Address Pool.

Example:

- **DHCP Start: 192.168.1.2**
- **DHCP End: 192.168.1.100**
- **Current DHCP Range: 192.168.1.2 – 192.168.1.100**