

Installing and Configuring Fairshift

Download Fairshift v21, unzip the FairShiftV21.rar file and save the installer executable to a suitable area on the C drive e.g. C:\Sierra\FairShiftV21.


Run the installer executable “FairShiftSetup.exe”




Select the optional additional shortcut and click “Next”



You should see the ready to install window:



Click install and you should see a demo limit message box




Click OK to get rid of the message box


You should get a SlimDX Runtime popup, click next.




The installer will install the runtime and you should see a confirmation window. Click on the Finish button to close the window.



Go back to the Fairshift setup window and click next:




Click on the finish button to complete the installation




Fairshift should be installed in C:\Sierra\FairShift

When Fairshift launches for the first time you need to setup the controllers:


If you get an error message it is because Fairshift needs to be run as an Administrator



To run Fairshift as an administrator. Goto the location where the executable is stored (C:\Sierra\FairShift) and RH mouse click to bring up the menu and select Properties.




Goto the Compatibility tab. Tick the option to “Run this program as an administrator” and click OK.




Double Click on the Fairshift.exe to run Fairshift.


A window will appear with the controllers Fairshift has detected but the names may be wrong. In this example a Thrustmaster T300 wheel and a Thrustmaster TH8A shifter are in separate USB ports. The Thrustmaster pedals are physically plugged into the Thrustmaster wheel so the clutch pedal uses the same USB port as the wheel. The names displayed are:




Select the T500 RS Gear for the H-Shifter and Thrustmaster for the clutch.



The next thing to do is to set up the H-Shifter Buttons, select Custom from the drop down list. Make sure the “Enable clutch” box is ticked to enable the cluch to be configured.



Clicking on the Custom Option in the drop down list should bring up a configuration window.




Pressing the clutch pedal will move one of the sliders (0 or 1) which identifies the clutch axis. Select the clutch axis from the drop down list.


Moving the H-Shifter into a gear will populate the Active Button display box. To assign the correct buttons just type in the button number against the associated gear.

Then click Done.

Once the clutch is configured it can disabled. If you don't want to use the clutch, simply uncheck the tick box. Before starting GPL, start Fairshift by pressing the start button. The status should change to "waiting for GPL"



Run GPL and the H-Shifter gears should be working in the game. After closing GPL the status of Fairshift changes to "gpl has stopped"




You can now close Fairshift using the x button on the top right corner of the window.


More than Two USB Devices?

If you have your wheel, pedals and H-shifter plugged into separate USB ports you may not be able to see all three controllers in the Fairshift window. Resizing the Window does not help.


In this example a third controller (an Xbox Controller) has been installed but it is not visible in the Fairshift Window:




So to select the XBox controller as the H-Shifter, first select Thrustmaster with the mouse click:




Then on the keyboard use the "Shift" and "down arrow" keys to move to the next Button:




Using the "Shift" and "down arrow" keys again, select the XBox controller which can't be seen



The Thrustmaster wheel is visible so the mouse is used to select it for the clutch



Then click on DONE and the flowing window appears



The H shift device and clutch can then be configured as described above.

Please note this exercise was for illustrative purposes only, using an Xbox controller for the gears is not recommended!

Compatibility with GPL Shift

GPL Shift has other facilities such as cockpit view adjustments which means a driver may not want to uninstall GPL Shift when using Fairshift. However, the shifter facility in GPL Shift must be disabled otherwise it will override Fairshift.

To disable the shifter facility in GPL Shift, open the “GPLshift.ini” file (located in the “C:\Sierra\GPL” folder) and make sure the shifter model is set to NONE:

[Shifter Unit]----------

Shifter_Model = NONE;

Demonstration Video

This YouTube video demonstrates how to configure the controls and run Fairshift with GPL.