

Motion HMI App

HMI for Robotic and CNC Applications

Version 4.6.0

Copyright

© Bosch Rexroth AG 2026

All rights reserved, also regarding any disposal, exploitation, reproduction, editing, distribution, as well as in the event of applications for industrial property rights.

Disclaimer

The specified data only serves to describe the product. As our products are constantly being further developed, no statements concerning a certain condition or suitability for a certain application can be derived from our information. The information given does not release the user from the obligation of own judgment and verification. Please note that our products are subject to a natural process of wear and aging.

DC-AE/PAD-SYS (MiSc/MePe)

Table of contents

1	About this documentation	4
2	Important information	4
2.1	Product information	4
3	Version 4.6.0	4
3.1	New functions	4
3.1.1	Feature 1131732: Support of static and dynamic translations for Motion HMI for the languages English and German	4
3.1.2	Feature 1131733: The user can configure the slider widget in the Motion HMI	5
3.1.3	Feature 1132738: The active kinematics can be assigned to a project or widget	5
3.1.4	Feature 1132741: Active file can be assigned to the project or to the file widget	5
3.1.5	Feature 1142709: ctrlX Dashboard widgets can be configured in the Motion HMI	6
3.1.6	Feature 1142740: The Motion HMI screen can be started in full screen mode via a URL	6
3.1.7	Feature 1142762: The user can copy projects, screens and designs	6
4	Service and support	7
5	Index	9

1 About this documentation

Editions of this documentation

Edition	Release date	Note
01	2026-03	Motion HMI App version 4.6.0

Further information

- See Motion HMI App, Application Manual (being edited)
- See → [Motion App, Application Manual](#)

2 Important information

2.1 Product information

For the latest information on our products, go to → <https://www.boschrexroth.com>.

For current security advisories, please refer to → <https://psirt.bosch.com/security-advisories/>

3 Version 4.6.0

3.1 New functions

3.1.1 Feature 1131732: Support of static and dynamic translations for Motion HMI for the languages English and German

Description

Motion HMI now supports static and dynamic translations to enable multilingual user interfaces.

1. Dynamic translation

Configuring translation identifiers

A translation icon is available in the project card that redirects users to the translation page.

Users can create translation IDs and define corresponding translation values for supported languages such as English (en) and German (de). These translations are saved in the app data files (en.json and de.json). Once a translation ID has been created, the name of the ID can no longer be changed.

Automatic translation for widgets

When button or label widgets are added to a screen, translation IDs are automatically generated and saved in the translation files.

The ID has the format: **ScreenName.ID**. These IDs and their values are automatically added to the translation structure under "Manage app data".

Assignment of translations to widgets

Users can assign translation IDs via the "Variable Text" configuration. Clicking on the browser icon opens a dialog that displays all available translation IDs. The IDs of the current screen are displayed by default. Users can activate "Show all IDs" to display IDs of all screens. After selecting an ID and clicking on "Assign ID", the translation is applied to the widget.

Translations are applied in execution mode or in full screen mode. Users can toggle between the supported languages (e.g. English and German). The user interface is updated dynamically according to the selected language.

2. Translation of static texts

Static UI texts are translated using the translation files:

- en.json
- de.json

If the language is changed, the application automatically loads the corresponding translation file.

3.1.2 **Feature 1131733: The user can configure the slider widget in the Motion HMI**

Description

The slider widget allows the user to select a value from a continuous or discrete range by moving a slider along a scale.

The user can configure "Actual value", "Minimum value" and "Maximum value" as values or the user can configure the Data Layer. The user can also configure the "step width".

3.1.3 **Feature 1132738: The active kinematics can be assigned to a project or widget**

Description

Configuring active kinematics at project level:

- The user can define the active kinematics at project level by editing the project properties.
- By default, the first kinematics is the active kinematics.
- The user can configure a Data Layer node so that the active kinematics are written to this Data Layer node when the screen is started.

Selecting kinematics at widget level:

- Fixed kinematics
 - Select a kinematics by name from a list of all configured kinematics.
 - These kinematics are permanently saved as a property of this widget.
 - The widget always displays the data for this kinematics irrespective which active kinematics is selected.
- Active kinematics:
 - This is a placeholder for variable kinematics that can be changed at runtime.
 - The configuration is permanently saved as property of this widget.
 - The active kinematics is a global property of a project and applies to all widgets in the project for which an active kinematics is configured.

Changing active kinematics:

- The user can change the active kinematics via button events.
- The button has an action for the OnMouseClicked event "Specify active kinematics".
- The active kinematics remain as long as the browser instance is active.
- The user can configure a Data Layer node to write the active kinematics to the Data Layer node when the "Specify active kinematics" event occurs.

The active kinematics should be displayed in the status bar widget.

3.1.4 **Feature 1132741: Active file can be assigned to the project or to the file widget**

Description

Select "Active file" in the file widget:

- The user can configure the active file for the kinematics in the file widget via a special button in the "Action" column.
- The user can configure a Data Layer node to read the active file from the Data Layer node or write to it when the active file is changed in the file widget.

Configure the "Active file" Data Layer node at project level:

- The user can configure a Data Layer node to read the active file from the Data Layer node when starting the screen.

3.1.5 **Feature 1142709: ctrlX Dashboard widgets can be configured in the Motion HMI**

Description

ctrlX Dashboard widgets are dynamically loaded into the Motion HMI widget list under the "ctrlX OS Widget" section. The user can configure them like any other widget in Motion HMI screens.

The properties provided by the widget can be configured in the "Properties" section of the wizard.

3.1.6 **Feature 1142740: The Motion HMI screen can be started in full screen mode via a URL**

Description

The Motion HMI screen can be started in full screen mode via a URL by attaching the query parameter **? fullscreen=true** to the URL.

3.1.7 **Feature 1142762: The user can copy projects, screens and designs**

Description

The user can create copies of projects, screens and designs in the respective screen.

The user has to enter a unique name. The copy of the project/screen/topic is saved in "Manage app data".

4 Service and support

Our worldwide service network provides an optimized and efficient support. Our experts provide you with advice and assistance. You can contact us **24/7**.

Service Germany

Our technology-oriented Competence Center in Lohr, Germany, is responsible for all your service-related queries for electric drive and controls.

Contact the **Service Hotline** and **Service Helpdesk** under:

Phone: **+49 9352 40 5060**

Fax: **+49 9352 18 4941**

Email: [↗ service.svc@boschrexroth.de](mailto:service.svc@boschrexroth.de)

Internet: [↗ http://www.boschrexroth.com](http://www.boschrexroth.com)

Additional information on service, repair (e.g. delivery addresses) and training can be found on our internet sites.

Service worldwide

Outside Germany, please contact your local service office first. For hotline numbers, refer to the sales office addresses on the internet.

Preparing information

To be able to help you more quickly and efficiently, please have the following information ready:

- Detailed description of malfunction and circumstances
- Type plate specifications of the affected products, in particular type codes and serial numbers
- Your contact data (phone and fax number as well as your e-mail address)

5 Index

A

About this documentation	4
Active file can be assigned to the project or to the file widget	5

C

ctrlX Dashboard widgets can be configured in the Motion HMI	6
---	---

F

Feature 1131732	4
Feature 1131733	5
Feature 1132738	5
Feature 1132741	5
Feature 1142709	6
Feature 1142740	6
Feature 1142762	6

H

Helpdesk	7
Hotline	7

I

Important information	4
---------------------------------	---

N

New functions version 4.6.0	4
---------------------------------------	---

P

Product information	4
-------------------------------	---

S

Service hotline	7
Support	7
Support of static and dynamic translations for Motion HMI for the languages English and German	4

T

The active kinematics can be assigned to a project or widget	5
The Motion HMI screen can be started in full screen mode via a URL	6
The user can configure the slider widget in the Motion HMI	5
The user can copy projects, screens and designs	6

Bosch Rexroth AG
Bgm.-Dr.-Nebel-Str. 2
97816 Lohr a.Main
Germany
Tel. +49 9352 18 0
Fax +49 9352 18 8400
www.boschrexroth.com/electrics

