

```
ROUTER

User Access Verification

Password:
ROUTER#
ROUTER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#line console 0
ROUTER(config-line)#password console
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#
*Aug 19 11:50:48.924: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#
```

```
Administrator: Command Prompt
Microsoft Windows [Version 6.1.
Copyright (c) 2009 Microsoft Co...

C:\Users\User>
C:\Users\User> ping 50.0.0.1

Pinging 50.0.0.1 with 32 bytes of data:
Reply from 50.0.0.1: bytes=32 time=1ms TTL=64
Reply from 50.0.0.1: bytes=32 time=1ms TTL=64
Reply from 50.0.0.1: bytes=32 time=1ms TTL=64
Reply from 50.0.0.1: bytes=32 time=1ms TTL=64

Ping statistics for 50.0.0.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in ms:
        Minimum = 0ms, Maximum = 1ms, Average = 1ms


C:\Users\User>
C:\Users\User>
```

```
ROUTER

Press RETURN to get started.

User Access Verification

Password:
ROUTER#enable
ROUTER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#username console password console
ROUTER(config)#line console 0
ROUTER(config-line)#password testconsole
ROUTER(config-line)#login local
ROUTER(config-line)#exit
ROUTER(config)#
```



```
Administrator: Command Prompt
Microsoft Windows [Version 6.1.7601]
Copyright (c) 2009 Microsoft Corporation. All rights reserved.

C:\Users\User>
C:\Users\User> ping 50.0.0.1

Pinging 50.0.0.1 with 32 bytes of data:
Reply from 50.0.0.1: bytes=32 time=1ms TTL=255
Reply from 50.0.0.1: bytes=32 time=1ms TTL=255
Reply from 50.0.0.1: bytes=32 time=1ms TTL=255
Reply from 50.0.0.1: bytes=32 time=1ms TTL=255

Ping statistics for 50.0.0.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\Users\User>
C:\Users\User>
C:\Users\User>
```

Press RETURN to get started.

User Access Verification

Username: console

Password:

Router Configuration

Physical ☐ ☐ ☐

