






```
R3#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R3(config)#ip dhcp pool HR
R3(dhcp-config)#network 29.0.0.0 255.0.0.0
R3(dhcp-config)#default-router 29.0.0.1
R3(dhcp-config)#dns-server 8.8.8.8
R3(dhcp-config)#lease 1 2 3
R3(dhcp-config)#exit
R3(config)#
R3(config)#ip dhcp excluded-address 29.0.0.1 29.0.0.50
R3(config)#exit
R3#
*Sep  4 05:38:40.357: %SYS-5-CONFIG_I: Configured from console by console
R3#
```






```
R3#show ip binding
^
% Invalid input detected at '^' marker.

R3#show ip dhcp binding
Bindings from all pools not associated with VRF:
IP address      Client-ID/      Lease expiration    Type
                Hardware address/
                User name
29.0.0.51       0150.cd1b.06ad.00  Sep 05 2026 01:17 PM Automatic
R3#
```

```
R3
R3#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#ip dhcp pool Sales
R3(dhcp-config)#network 1.0.0.0 255.0.0.0
R3(dhcp-config)#default-router 1.0.0.1
R3(dhcp-config)#dns-router 8.8.8.8
      ^
% Invalid input detected at '^' marker.

R3(dhcp-config)#dns-server 8.8.8.8
R3(dhcp-config)#lease 1 2 3
R3(dhcp-config)#exit
R3(config)#
R3(config)#ip dhcp excluded-address 1.0.0.1 1.0.0.50
R3(config)#exit
R3#
R3#
R3#co
*Sep  4 05:51:44.070: %SYS-5-CONFIG_I: Configured from console by console
R3#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#ip dhcp pool PRODUCTION
R3(dhcp-config)#network 212.25.0.0 255.255.255.0
R3(dhcp-config)#default-router 212.25.0.1
R3(dhcp-config)#dns-server 8.8.8.8
R3(dhcp-config)#lease 1 2 3
R3(dhcp-config)#exit
R3(config)#
R3(config)#ip dhcp excluded-address 212.25.0.1 212.25.0.50
R3(config)#exit
R3#
*Sep  4 05:55:00.146: %SYS-5-CONFIG_I: Configured from console by console
R3#
R3#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#
R3(config)#ip dhcp pool MGMT
R3(dhcp-config)#network 129.23.0.0 255.255.0.0
R3(dhcp-config)#default-router 129.23.0.1
R3(dhcp-config)#dns-server 8.8.8.8
R3(dhcp-config)#lease 1 2 3
R3(dhcp-config)#exit
R3(config)#
R3(config)#ip dhcp excluded-address 129.23.0.1 129.23.0.50
R3(config)#exit
```

```
R1
R1(config)#
*Sep  8 07:20:50.655: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1(config)#ip route 29.0.0.0 255.0.0.0 172.50.0.2
R1(config)#ip route 12.0.0.0 255.0.0.0 172.50.0.2
R1(config)#exit
R1#
R1#
R1#
*Sep  8 07:23:34.262: %SYS-5-CONFIG_I: Configured from console by console
R1#
R1#
R1#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#
R1(config)#
R1(config)#
R1(config)#interface ethernet0/1
R1(config-if)#ip helper-address 12.0.0.2
R1(config-if)#exit
R1(config)#
R1(config)#
R1(config)#
R1(config)#
```



QEMU (Win-4)



My Documents

My Computer

My Network Places

Recycle Bin

Internet Explorer

Cisco ASDM-1...

```
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 212.25.0.101
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 212.25.0.1

C:\Documents and Settings\user>
```

QEMU (Win-3)

