


1. Download and Install Dosbox according to your operating system.
2. Run Dosbox
3. Download and extract [following folder](#)
4. Create a new folder anywhere.
5. From the extracted folder copy masm.exe, debug.exe and link.exe to this new folder.
6. Now from Dos box mount this folder



The screenshot shows a DOSBox window titled "DOSBox 0.74-3, Cpu speed: 3000 cycles, Frameskip 0, Program: DOSBOX". The main window has a blue background with white text. It displays a welcome message: "Welcome to DOSBox v0.74-3", followed by instructions for new users to type "INTRO" and for supported shell commands to type "HELP". It also provides information on adjusting CPU speed (ctrl-F11 and ctrl-F12), activating the keymapper (ctrl-F1), and reading the README file. At the bottom, it says "HAVE FUN!" and "The DOSBox Team http://www.dosbox.com". Below the welcome message, the command prompt shows the following commands and their outputs: "Z:\>SET BLASTER=A220 I7 D1 H5 T6", "Z:\>mount c /home/janak/Documents/8086", "Drive C is mounted as local directory /home/janak/Documents/8086/", "Z:\>c:", and "C:\>_".

```
DOSBox 0.74-3, Cpu speed: 3000 cycles, Frameskip 0, Program: DOSBOX

Welcome to DOSBox v0.74-3

For a short introduction for new users type: INTRO
For supported shell commands type: HELP

To adjust the emulated CPU speed, use ctrl-F11 and ctrl-F12.
To activate the keymapper ctrl-F1.
For more information read the README file in the DOSBox directory.

HAVE FUN!
The DOSBox Team http://www.dosbox.com

Z:\>SET BLASTER=A220 I7 D1 H5 T6

Z:\>mount c /home/janak/Documents/8086
Drive C is mounted as local directory /home/janak/Documents/8086/

Z:\>c:
C:\>_
```

7. Open editor or note pad and write following code.

```
.model small
.stack 100h
.data
    msg db 'Hello$'
.code
main proc
    mov ax, @data
    mov ds, ax


    lea dx, msg
    mov ah, 09h
    int 21h

    mov ah, 4ch
    int 21h
main endp
end main
```

8. Save it as hello.asm
9. Type following commands Dosbox

masm hello2.asm;
link hello2.link;
hello2.exe

10. Output



```
DOSBox 0.74-3, Cpu speed: 3000 cycles, Frameskip 0, Program: DOSBOX - x

50630 + 465914 Bytes symbol space free

0 Warning Errors
0 Severe Errors

C:\>masm hello2.asm;
Microsoft (R) Macro Assembler Version 5.00
Copyright (C) Microsoft Corp 1981-1985, 1987. All rights reserved.

51698 + 464846 Bytes symbol space free

0 Warning Errors
0 Severe Errors

C:\>link hello2.obj;

Microsoft (R) Overlay Linker Version 3.60
Copyright (C) Microsoft Corp 1983-1987. All rights reserved.

C:\>hello2.exe
Hello
C:\>
```