Launch Control XL 3 — Track 007 — ambient moods

Dreamy ambient on D, about 70 BPM. Jojo plays the foundation (heartbeat, drone, bass and soft clicks), Jonas the colour (pad, bowed loops, marimba and toms, choir, sparkles) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar, 3 per stem), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up.

Every Launch Control XL 3 gets this full layout: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Crackle) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages. Two controllers: the control moved last wins.

Knob | Fader | Button | global (all modes) | unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Pulse	2 Sea / Wind	3 Drone	4 Bass	5 Rim	6 Shaker	7 Wood / Drops	8 Global
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright.	CC 14 **Brightness** dull ↔ bright.	CC 15 **Brightness** dull ↔ bright.	CC 16 **Brightness** dull ↔ bright.	CC 17 **Brightness** dull ↔ bright.	CC 18 **Brightness** dull ↔ bright.	CC 19 **Brightness** dull ↔ bright.	CC 20 **Fog** clear ↔ muffled (all low-passes down).
Row 2 Space	CC 21 **Space** dry ↔ room.	CC 22 **Space** dry ↔ room.	CC 23 **Space** dry ↔ room.	CC 24 **Space** dry ↔ room.	CC 25 **Space** dry ↔ room.	CC 26 **Space** dry ↔ room.	CC 27 **Space** dry ↔ room.	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Punch** three steps: soft sine thump → synth kick → firm kick with more click.	CC 30 **Sea ↔ Wind** 0 = brown-noise waves rolling in, 0.5 = both, 1 = only whistling wind gusts.	CC 31 **Beating** pure sines ↔ detuned saw beating.	CC 32 **Groove** 0 = a soft swell every bar. Up to 0.5 a 3-3-2 pulse fades in, at 1 only the pulse.	CC 33 **Complexity** plain ↔ extra quiet clicks in between.	CC 34 **Complexity** 0 = the figure ↔ + quiet 16ths, from the middle a cabasa on 4.	CC 35 **Complexity** a click now and then ↔ a busy pattern.	CC 36 **Tension** build-up: echo, reverb, open filters; the end adds a snare roll.
Fader Level	CC 5 **Level** 0 = gone. A heartbeat thump on D.	CC 6 **Level** sea and wind. Keeps playing in the break.	CC 7 **Level** slow drone chords on D.	CC 8 **Level** slow bass swells.	CC 9 **Level** soft rim click on 2 and 4.	CC 10 **Level** shaker.	CC 11 **Level** wood clicks and drops.	CC 12 **Master** volume of everything.
Button 1 Change	CC 37 **Pattern** heartbeat → quarters → half notes.	CC 38 **Pattern** next of 3 random wave / gust patterns.	CC 39 **Pattern** 3 drone chords per chapter: D–A → D–A–E → G–D–A.	CC 40 **Pattern** next of 3 bass lines (a note every 2 bars).	CC 41 **Pattern** backbeat → late ghost → offset click.	CC 42 **Pattern** 8ths → 16ths → rocking 3-3-2.	CC 43 **Pattern** next of 3 random patterns.	CC 44 **Chapter** mood: floating → melancholic → strange, at the next bar.
Button 2 Moment	CC 45 **Drop out** pulse pauses while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 —	CC 48 **Octave** one octave up while held.	CC 49 **Roll** 16th roll, growing over the bar, while held.	CC 50 **Echo throw** held: long dotted-8th echo.	CC 51 **Fill** almost every 16th plays while held.	CC 52 **Break** 1st: low end out. 2nd: all back on the one.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Pad	2 Eno / Shimmer	3 Marimba	4 Toms	5 Choir	6 Glitter	7 Voice	8 Global
Row 1 Brightness	CC 61 **Brightness** dull ↔ bright.	CC 62 **Brightness** dull ↔ bright.	CC 63 **Brightness** dull ↔ bright.	CC 64 **Brightness** dull ↔ bright.	CC 65 **Brightness** dull ↔ bright.	CC 66 **Brightness** dull ↔ bright.	CC 67 **Brightness** dull ↔ bright.	CC 20 **Fog** clear ↔ muffled (all low-passes down).
Row 2 Space	CC 69 **Space** dry ↔ echo + room.	CC 70 **Space** dry ↔ echo + room.	CC 71 **Space** dry ↔ echo + room.	CC 72 **Space** dry ↔ echo + room.	CC 73 **Space** dry ↔ echo + room.	CC 74 **Space** dry ↔ echo + room.	CC 75 **Space** dry ↔ echo + room.	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Swell** still chords ↔ re-struck and breathing.	CC 78 **Complexity** more loops; the shimmer adds a bell chord.	CC 79 **Complexity** one figure ↔ all layers.	CC 80 **Complexity** 0 = the figure alone ↔ fuller: rests fill up, canon voices, a drifting copy.	CC 81 **Complexity** 0 = one voice, 0.5 = + a third above, 1 = + a fifth: three-part harmony.	CC 82 **Complexity** a drop now and then (~1 per bar) ↔ a sparkling rain (~70 % of the 16ths).	CC 83 **Distortion** radio → rougher → past half: crushed, broken.	CC 36 **Tension** build-up: echo, reverb, open filters; the end adds a snare roll.
Fader Level	CC 53 **Level** long floating chords.	CC 54 **Level** bowed loops (low) and shimmer swells (high).	CC 55 **Level** marimba figures laid over each other (Takada).	CC 56 **Level** tom figures.	CC 57 **Level** choir voices.	CC 58 **Level** random glockenspiel notes.	CC 59 **Level** the spoken voice, looping.	CC 12 **Master** volume of everything.
Button 1 Change	CC 85 **Pattern** 3 chord progressions: calm → circling → open.	CC 86 **Pattern** note set: calm → lydian → low; shimmer pace too.	CC 87 **Pattern** cycles → canon → cells → Euclid → build-up.	CC 88 **Pattern** cycles → canon → Euclid → build-up → crossing → Clapping.	CC 89 **Pattern** middle → low → high register (new melody each time).	CC 90 **Pattern** high → very high → middle register.	CC 91 —	CC 44 **Chapter** mood: floating → melancholic → strange, at the next bar.
Button 2 Moment	CC 93 **Freeze** holds the current chord while held.	CC 94 **Layer** Eno → Shimmer → both, at the next bar.	CC 95 **Echo throw** held: long dotted-8th echo.	CC 96 **Echo throw** held: long dotted-8th echo.	CC 97 **Full choir** all three voices while held.	CC 98 **Run** scale runs, denser while held.	CC 99 **Stutter** held: each beat's start repeats in 16ths.	CC 52 **Break** 1st: low end out. 2nd: all back on the one.

Guide

Playing together

Jojo builds the floor: drone and bass first, then the heartbeat, then the small clicks. Jonas colours it: pad and bowed loops, marimba and toms for movement, then choir and the sparkles on top.

Jonas' column 8 acts on everything: Fog and Tension darken or open all filters, Room drowns everything in reverb, Chapter changes the key colour for both players at the next bar.

Break: one press takes out the beat (pulse, bass, rim, shaker, wood) at the next bar; drone, crackle, sea and all of Jonas' sounds keep floating. The second press brings the beat back on the one.

Both Launch Controls have the full layout and steer the same sounds: whoever moves a control last sets its value, a button press counts from either. Agree who plays which page.

Every position sounds good

No filter closes completely, and space 0 is dry but never silent. Row 2 at about the middle gives each sound the room it had in the original track.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.