Launch Control XL 3 — Track 008 — groove techno (one controller)

Groove techno on F, 140 BPM. Jojo plays the foundation (kick, bass, drums), Jonas the colour (pad, chord pulse, melodies) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Jonas' pad button 1 changes the chords, and Jojo's sub and bassline follow.

One controller: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Ride) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages.

Knob Fader Button global (all modes) unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Kick	2 Rumble	3 Sub	4 Bassline	5 Clap	6 Hats	7 Percussion	8 Global
Row 1 Brightness	CC 13 **Brightness** 0 = round but clear ↔ clicky attack (lpf 900–9000 Hz).	CC 14 **Brightness** 0 = warm rumble ↔ more of the kick's body in the tail (lpf 250–1800 Hz).	CC 15 **Brightness** 0 = sine with a few overtones (audible on small speakers) ↔ warm and full.	CC 16 **Brightness** 0 = round ↔ raw and buzzing (lpf 400–3000 Hz).	CC 17 **Brightness** soft and far ↔ sharp crack (lpf 1.5–12 kHz).	CC 18 **Brightness** soft hiss ↔ crisp and sharp (lpf 3–16 kHz).	CC 19 **Brightness** woody ↔ metallic (FM and lpf 600–12000 Hz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from the room next door.
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** short rumble ↔ a long dark cloud (reverb never fully off: the reverb is the sound).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ a little room (reverb).	CC 25 **Space** dry ↔ far away (reverb).	CC 26 **Space** dry ↔ far away (reverb).	CC 27 **Space** dry ↔ far away (reverb).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Punch** 0 = really soft thump, middle = round kick, 1 = hard and punchy.	CC 30 **Motion** still ↔ the filter breathes and the rumble echoes in 16ths.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Groove** off-beats only ↔ extra 16th notes bouncing in between.	CC 33 **Ghost notes** plain ↔ a quiet clap before beat 3 ↔ + small double taps.	CC 34 **Density** the pattern as it is ↔ + quiet 16ths ↔ + little 32nd rolls.	CC 35 **Density** steady pattern ↔ + fingertip ghost notes ↔ + little rolls.	CC 36 **Tension** build-up: echo grows (answer, sequence), filters open (not hats, clap, ride), only in the last fifth a snare roll (clap fader). 0 = release.
Fader Level	CC 5 **Level** 0 = gone. Kick on every beat, tuned to C (fifth of F).	CC 6 **Level** rumble under the kick, same pitch (C).	CC 7 **Level** pumping sub, follows Jonas' chords.	CC 8 **Level** off-beat bass, follows Jonas' chords.	CC 9 **Level** clap on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** hats. Keep playing in the break.	CC 11 **Level** bongos and rimshot. Keep playing in the break.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** straight → ghost kick before the 1 → gap every 4th bar.	CC 38 **Change** 3rd + 4th 16th → 2nd–4th → only the 3rd.	CC 39 **Change** pump → fifth on beat 4 → syncopated.	CC 40 **Change** off-beat → 3-3-2 → dub.	CC 41 **Change** short clap → with pickup → full drop clap (tail + double).	CC 42 **Change** off-beat → plain 16ths → driving.	CC 43 **Change** pillow → gallop → 3-3-2.	CC 44 **Chapter** mood: warm → dark → tense, at the next bar.
Button 2 Moment	CC 45 **Drop out** kick pauses while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 **Slide** every note bends up into its pitch while held.	CC 48 **Octave** one octave up while held.	CC 49 **Swell** snare swell over 4 bars while held.	CC 50 **Open** open hats on the off-beats while held.	CC 51 **Fill** a bongo run down over the bar while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Pad	2 Chord Pulse	3 Sequence	4 Lead	5 Answer	6 Pings	7 FX / Breath	8 Global
Row 1 Brightness	CC 61 **Brightness** muffled ↔ open and airy (lpf 250–6000 Hz).	CC 62 **Brightness** muffled ↔ open (lpf 300–5000 Hz).	CC 63 **Brightness** soft wooden mallet ↔ sharp, glassy (lpf 1.5–12 kHz, more FM).	CC 64 **Brightness** dark pluck ↔ open and clear (lpf 600–6000 Hz, breathing slowly).	CC 65 **Brightness** soft ↔ clear and bright (lpf 2–12 kHz).	CC 66 **Brightness** dark, woody plink ↔ bright, biting bell (lpf 1–8 kHz).	CC 67 **Brightness** dark whoosh ↔ bright hiss (lpf 1.5–14 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from the room next door.
Row 2 Space	CC 69 **Space** dry and close ↔ far away in a big room (reverb).	CC 70 **Space** dry and close ↔ far away (reverb).	CC 71 **Space** a little room and echo ↔ far away (reverb + dub echo).	CC 72 **Space** a little room ↔ far away (reverb).	CC 73 **Space** some room and echo ↔ far away in space.	CC 74 **Space** dry ↔ far away (reverb).	CC 75 **Space** nearly dry ↔ far away (reverb).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Swell** 0 = held chords. Up = the chord is re-struck on every half bar and breathes in and out.	CC 78 **Motion** a few soft pulses ↔ more pulses join one by one, denser and more syncopated.	CC 79 **Complexity** few notes ↔ the loop fills in and new notes join one by one, reaching further up and down.	CC 80 **Variation** the phrase as written ↔ notes repeat in quick 16ths and step to their neighbours, at random.	CC 81 **Voices** 0 = one voice, 0.4 = + a third, 0.75 = + a fifth ↔ top: + the 7th, the voices strum apart and the phrase spills into the other bars.	CC 82 **Density** the figure alone ↔ at 0.75 the gaps filled in at random ↔ top quarter: quick 32nd doubles.	CC 83 **Amount** 0 = only the breathing noise. Up = the chord pulses along in loose 8ths, at 1 also a 16th shimmer an octave up.	CC 36 **Tension** build-up: echo grows (answer, sequence), filters open (not hats, clap, ride), only in the last fifth a snare roll (clap fader). 0 = release.
Fader Level	CC 53 **Level** dark pad.	CC 54 **Level** the pad's chords as soft pulses.	CC 55 **Level** hypnotic loop on the chord.	CC 56 **Level** lead line on the chord.	CC 57 **Level** counter blips, a short phrase every second bar.	CC 58 **Level** high bell riff.	CC 59 **Level** slow, uneven breathing.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 85 **Change** next of 8 chord progressions, for all.	CC 86 **Change** next of 8 pulse rhythms.	CC 87 **Change** next of 8 loops (3, 5 or 7 steps).	CC 88 **Change** next of 8 four-bar phrases.	CC 89 **Change** next of 8 phrase rhythms (new notes too).	CC 90 **Change** next of 8 bell figures (rhythm + notes).	CC 91 **Change** one breath per 2 → 4 → 8 → 1 bar(s).	CC 44 **Chapter** mood: warm → dark → tense, at the next bar.
Button 2 Moment	CC 93 **Freeze** holds the current chord while held, for everybody.	CC 94 **Echo throw** long echo on the pulses while held.	CC 95 **Octave** one octave up while held.	CC 96 **Echo throw** long echo on the line while held.	CC 97 **Answer** random extra answers while held.	CC 98 **Run** up and down the chord, fuller the longer it is held.	CC 99 **Open** the breath opens fully while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Playing together

Jojo builds the floor: kick first, rumble right next to it, then sub and hats, then clap, bassline and the groove (percussion, ride).

Jonas colours it: pad first, then the chord pulse under it (all knobs at 0 is a good start), then the sequence. Lead, answer and pings are for the peaks, the breathing FX for long transitions.

The pad's button 1 changes the chords for both players: Jojo's sub and bassline move with it. Pad button 2 (freeze) holds the chord for everybody.

Break: one press takes out kick, rumble, sub, bassline and clap at the next bar; hats, percussion, ride and all of Jonas' sounds keep going. Turn Tension up during the break, press again: everything is back on the one. Then let Tension go.

Every position sounds good

No filter closes completely. Sequence, answer and FX keep a little room even at space 0.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.