Launch Control XL 3 — Track 007 — ambient moods

Dreamy ambient on D, about 70 BPM. Jojo plays the foundation (heartbeat, drone, bass and soft clicks), Jonas the colour (pad, bowed loops, marimba and toms, choir, sparkles) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar, 3 per stem), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up.

Every Launch Control XL 3 gets this full layout: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Crackle) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages. Two controllers: the control moved last wins.

Knob | Fader | Button | global (all modes) | unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Pulse	2 Sea / Wind	3 Drone	4 Bass	5 Rim	6 Ticks	7 Wood / Drops	8 Global
Row 1 Brightness	CC 13 **Brightness** dull thump ↔ clicky attack (lpf 180–1500 Hz).	CC 14 **Brightness** 0 = soft rumble ↔ airy hiss (lpf 700–12000 Hz, moves with the waves).	CC 15 **Brightness** pure and dark ↔ open, the overtones come through (lpf 120–4000 Hz).	CC 16 **Brightness** round and dark ↔ the saw's buzz comes through (lpf 80–2000 Hz).	CC 17 **Brightness** soft and far ↔ sharp crack (lpf 1.2–12 kHz).	CC 18 **Brightness** soft tick ↔ crisp and sharp (lpf 3–16 kHz).	CC 19 **Brightness** woody (pure sine blip) ↔ metallic (FM).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: distant, under water.
Row 2 Space	CC 21 **Space** dry and close ↔ far away in a big room (reverb).	CC 22 **Space** dry ↔ far away (reverb).	CC 23 **Space** dry ↔ far away (reverb).	CC 24 **Space** dry ↔ far away (reverb).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Drive** three steps: soft sine thump → synth kick → firm kick with more click.	CC 30 **Sea ↔ Wind** 0 = brown-noise waves rolling in, 0.5 = both, 1 = only whistling wind gusts.	CC 31 **Beating** 0 = pure sines. Up = a detuned saw copy fades in, the two beat against each other (slow “wah-wah”).	CC 32 **Groove** 0 = a soft swell every bar. Up to 0.5 a 3-3-2 pulse fades in, at 1 only the pulse.	CC 33 **Ghost notes** plain ↔ extra quiet clicks in between.	CC 34 **Density** 8ths ↔ + 16ths ↔ + little flutters.	CC 35 **Density** a click now and then ↔ a busy pattern.	CC 36 **Tension** 0–0.5: echo grows on all melodic stems, filters open. 0.5–1: + slow tape wobble on the long sounds. Back to 0 = release.
Fader Level	CC 5 **Level** 0 = gone. A heartbeat thump on D.	CC 6 **Level** sea and wind. Keeps playing in the break.	CC 7 **Level** slow drone chords on D.	CC 8 **Level** slow bass swells.	CC 9 **Level** soft rim click on 2 and 4.	CC 10 **Level** clock ticks.	CC 11 **Level** wood clicks and drops.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** heartbeat → quarters → half notes.	CC 38 **Change** next of 3 random wave / gust patterns.	CC 39 **Change** 3 drone chords per chapter: D–A → D–A–E → G–D–A.	CC 40 **Change** next of 3 bass lines (a note every 2 bars).	CC 41 **Change** backbeat → late ghost → offset click.	CC 42 **Change** next of 3 random accent / 16th patterns.	CC 43 **Change** next of 3 random patterns.	CC 44 **Chapter** mood: floating → melancholic → strange, at the next bar.
Button 2 Moment	CC 45 **Drop out** pulse pauses while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 —	CC 48 **Octave** one octave up while held.	CC 49 **Roll** 16th roll, growing over the bar, while held.	CC 50 **Open** ticks ring long while held.	CC 51 **Fill** almost every 16th plays while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Pad	2 Eno Bowed	3 Marimba	4 Toms	5 Choir	6 Glitter	7 Shimmer	8 Global
Row 1 Brightness	CC 61 **Brightness** muffled ↔ open and airy (lpf 300–8000 Hz).	CC 62 **Brightness** soft ↔ bright (lpf 800–12000 Hz).	CC 63 **Brightness** soft mallet ↔ bright (lpf 600–6000 Hz).	CC 64 **Brightness** soft ↔ bright (lpf 600–6000 Hz).	CC 65 **Brightness** hushed ↔ clear (lpf 500–10000 Hz).	CC 66 **Brightness** soft mallets ↔ bright metal (lpf 3–16 kHz).	CC 67 **Brightness** dark whoosh ↔ bright shimmer (lpf 1.5–14 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: distant, under water.
Row 2 Space	CC 69 **Space** dry and close ↔ far away in a big room (reverb + echo).	CC 70 **Space** room and dotted-8th echo (a little at 0).	CC 71 **Space** room and dotted-8th echo (a little at 0).	CC 72 **Space** room and dotted-8th echo (a little at 0).	CC 73 **Space** dry ↔ far away (reverb + echo).	CC 74 **Space** dry ↔ far away (reverb + echo).	CC 75 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Swell** 0 = still, held chords. Up = the chord is re-struck every half bar and breathes in and out.	CC 78 **Complexity** 2 loops ↔ 6 loops drifting against each other.	CC 79 **Complexity** 0 = one figure ↔ all layers (Euclid: also denser; build-up: up to 7, louder and brighter).	CC 80 **Complexity** 0 = the figure alone ↔ fuller: rests fill up, canon voices, a drifting copy.	CC 81 **Voices** 0 = one voice, 0.5 = + a third above, 1 = + a fifth: three-part harmony.	CC 82 **Density** a drop now and then (~1 per bar) ↔ a sparkling rain (~70 % of the 16ths).	CC 83 **Amount** subtle (one tone) ↔ wild (a bell-like chord with long echoes).	CC 36 **Tension** 0–0.5: echo grows on all melodic stems, filters open. 0.5–1: + slow tape wobble on the long sounds. Back to 0 = release.
Fader Level	CC 53 **Level** long floating chords.	CC 54 **Level** bowed vibraphone loops (Eno, Music for Airports).	CC 55 **Level** marimba figures laid over each other (Takada).	CC 56 **Level** tom figures.	CC 57 **Level** choir voices.	CC 58 **Level** random glockenspiel notes.	CC 59 **Level** shimmer swells.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 85 **Change** 3 chord progressions: calm → circling → open.	CC 86 **Change** note set: calm (fifths) → lydian (G♯, C♯) → low and slower.	CC 87 **Change** cycles → canon → cells → Euclid → build-up.	CC 88 **Change** cycles → canon → Euclid → build-up → crossing → Clapping.	CC 89 **Change** middle → low → high register (new melody each time).	CC 90 **Change** high → very high → middle register.	CC 91 **Change** a new tone every 2 bars → every 4 bars → every bar.	CC 44 **Chapter** mood: floating → melancholic → strange, at the next bar.
Button 2 Moment	CC 93 **Freeze** holds the current chord while held.	CC 94 **Echo throw** held: long dotted-8th echo.	CC 95 **Echo throw** held: long dotted-8th echo.	CC 96 **Echo throw** held: long dotted-8th echo.	CC 97 **Full choir** all three voices while held.	CC 98 **Run** runs up and down the scale, denser and louder the longer it is held (full after 2 bars).	CC 99 **Rise** while held, a cloud of tones climbs an octave and grows denser over 2 bars.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Playing together

Jojo builds the floor: drone and bass first, then the heartbeat, then the small clicks. Jonas colours it: pad and bowed loops, marimba and toms for movement, then choir and the sparkles on top.

Jonas' column 8 acts on everything: Fog and Tension darken or open all filters, Room drowns everything in reverb, Chapter changes the key colour for both players at the next bar.

Break: one press takes out the beat (pulse, bass, rim, ticks, wood) at the next bar; drone, crackle, sea and all of Jonas' sounds keep floating. The second press brings the beat back on the one.

Both Launch Controls have the full layout and steer the same sounds: whoever moves a control last sets its value, a button press counts from either. Agree who plays which page.

Every position sounds good

No filter closes completely, and space 0 is dry but never silent. Row 2 at about the middle gives each sound the room it had in the original track.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.