Launch Control XL 3 — Track 008 — groove techno

Groove techno on F minor, 140 BPM. Jojo plays the foundation (kick, bass, drums), Jonas the colour (pads, stab, percussion) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Jonas' pad button 1 changes the chords, and Jojo's sub and bassline follow.

Every Launch Control XL 3 gets this full layout: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Ride) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages. Two controllers: the control moved last wins.

Knob | Fader | Button | global (all modes) | unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Kick	2 Rumble	3 Sub	4 Bassline	5 Clap	6 Hats	7 Percussion	8 Global
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright.	CC 14 **Brightness** dull ↔ bright.	CC 15 **Brightness** dull ↔ bright.	CC 16 **Brightness** dull ↔ bright.	CC 17 **Brightness** dull ↔ bright.	CC 18 **Brightness** dull ↔ bright.	CC 19 **Brightness** dull ↔ bright.	CC 20 **Fog** clear ↔ muffled (all low-passes down).
Row 2 Space	CC 21 **Space** dry ↔ room.	CC 22 **Space** dry ↔ room.	CC 23 **Space** dry ↔ room.	CC 24 **Space** dry ↔ room.	CC 25 **Space** dry ↔ room.	CC 26 **Space** dry ↔ room.	CC 27 **Space** dry ↔ room.	CC 28 **Thin** full ↔ thin (all high-passes up).
Row 3 Character	CC 29 **Punch** 0 = really soft thump, middle = round kick, 1 = hard and punchy.	CC 30 **Motion** still ↔ the filter breathes and the rumble echoes in 16ths.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Complexity** the line as written ↔ quiet ghost 16ths roll in the gaps.	CC 33 **Complexity** plain ↔ a quiet clap before beat 3 ↔ + small double taps.	CC 34 **Complexity** the pattern as it is ↔ + quiet 16ths ↔ + little 32nd rolls.	CC 35 **Complexity** steady pattern ↔ + fingertip ghost notes ↔ + little rolls.	CC 36 **Tension** build-up: echo, reverb, open filters; the end adds a snare roll.
Fader Level	CC 5 **Level** 0 = gone. Kick on every beat, tuned to C (fifth of F).	CC 6 **Level** rumble under the kick, same pitch (C).	CC 7 **Level** pumping sub, follows Jonas' chords.	CC 8 **Level** dark rolling bass, follows Jonas' chords.	CC 9 **Level** clap on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** open hats. Keep playing in the break.	CC 11 **Level** bongos and rimshot. Keep playing in the break.	CC 12 **Master** volume of everything.
Button 1 Change	CC 37 **Double time** 8 kicks per bar instead of 4 while held.	CC 38 **Pattern** 3rd + 4th 16th → 2nd–4th → only the 3rd.	CC 39 **Pattern** pump → fifth on beat 4 → syncopated.	CC 40 **Pattern** 3-3-2 → rolling → acid → stomp.	CC 41 **Pattern** short clap → with pickup → full drop clap (tail + double).	CC 42 **Pattern** open off-beat → + closed 16ths → driving.	CC 43 **Pattern** pillow → gallop → 3-3-2.	CC 44 **Chapter** mood: dark → tense → warm, at the next bar.
Button 2 Moment	CC 45 **Drop out** kick pauses while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 **Octave** one octave up while held.	CC 48 **Octave** one octave up while held.	CC 49 **Swell** snare swell over 4 bars while held.	CC 50 **Long** the open hats ring longer, on every 8th, while held.	CC 51 **Fill** a bongo run down over the bar while held.	CC 52 **Break** 1st: low end out. 2nd: all back on the one.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Pads	2 Strings	3 Sequence	4 Stab	5 Answer	6 Dark Perc	7 FX / Breath	8 Global
Row 1 Brightness	CC 61 **Brightness** dull ↔ bright.	CC 62 **Brightness** dull ↔ bright.	CC 63 **Brightness** dull ↔ bright.	CC 64 **Brightness** dull ↔ bright.	CC 65 **Brightness** dull ↔ bright.	CC 66 **Brightness** dull ↔ bright.	CC 67 **Brightness** dull ↔ bright.	CC 20 **Fog** clear ↔ muffled (all low-passes down).
Row 2 Space	CC 69 **Space** dry ↔ echo + room.	CC 70 **Space** dry ↔ echo + room.	CC 71 **Space** dry ↔ echo + room.	CC 72 **Space** dry ↔ echo + room.	CC 73 **Space** dry ↔ echo + room.	CC 74 **Space** dry ↔ echo + room.	CC 75 **Space** dry ↔ echo + room.	CC 28 **Thin** full ↔ thin (all high-passes up).
Row 3 Character	CC 77 **Pump** 0 = held chords ↔ the kick pumps the chords on every beat.	CC 78 **Sound** JX-10 strings ↔ analogue strings (pulse + saw).	CC 79 **Complexity** few notes ↔ loop fills in.	CC 80 **Variation** as written ↔ quick 16ths, octave jumps.	CC 81 **Complexity** one voice → + third → + fifth → + 7th, strummed.	CC 82 **Complexity** claves → + ticks → + zaps → 32nds.	CC 83 **Complexity** breath only ↔ chord pulses in 8ths.	CC 36 **Tension** build-up: echo, reverb, open filters; the end adds a snare roll.
Fader Level	CC 53 **Level** the pads (pad + techno pad).	CC 54 **Level** background strings on F minor.	CC 55 **Level** hypnotic loop on the chord.	CC 56 **Level** hypnotic stab on the chord root.	CC 57 **Level** counter blips, a short phrase every second bar.	CC 58 **Level** dark fast percussion.	CC 59 **Level** slow, uneven breathing.	CC 12 **Master** volume of everything.
Button 1 Change	CC 85 **Pattern** next of 8 chord progressions, for all.	CC 86 **Pattern** next move: to D♭ · to A♭ · line up · line down · chain, at the next bar.	CC 87 **Pattern** next of 8 loops (3, 5 or 7 steps).	CC 88 **Pattern** next of 8 stab figures.	CC 89 **Pattern** next of 8 phrase rhythms (new notes too).	CC 90 **Pattern** next of 8 clave figures.	CC 91 **Pattern** one breath per 2 → 4 → 8 → 1 bar(s).	CC 44 **Chapter** mood: dark → tense → warm, at the next bar.
Button 2 Moment	CC 93 **Colour** 7 → 9 → fourths → fifths, at the next bar.	CC 94 **Echo throw** long echo on the strings while held.	CC 95 **Octave** one octave up while held.	CC 96 **Echo throw** long echo on the stab while held.	CC 97 **Answer** random extra answers while held.	CC 98 **Roll** shaker and metal roll in 32nds, fuller and louder the longer it is held.	CC 99 **Open** the breath opens fully while held.	CC 52 **Break** 1st: low end out. 2nd: all back on the one.

Guide

Playing together

Jojo builds the floor: kick first, rumble right next to it, then sub and hats, then clap, bassline and the groove (percussion, ride).

Jonas colours it: pads first (all knobs at 0 is a good start), then the strings in the background, then dark percussion and the sequence. Stab and answer are for the peaks, the breathing FX for long transitions.

The pad's button 1 changes the chords for both players: Jojo's sub and bassline move with it. Pad button 2 changes the chord colour (7, 9, fourths, fifths).

Break: one press takes out kick, rumble, sub, bassline and clap at the next bar; hats, percussion, ride and all of Jonas' sounds keep going. Turn Tension up during the break (its snare roll keeps playing), press again: everything is back on the one. Then let Tension go.

Both Launch Controls have the full layout and steer the same sounds: whoever moves a control last sets its value, a button press counts from either. Agree who plays which page.

Every position sounds good

No filter closes completely. Sequence, answer and FX keep a little room even at space 0.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 (chapter, break, tension) for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.