Launch Control XL 3 — Track 009 — house, variant riffs

Happy, jazzy, dry house in A minor, 124 BPM. Jojo plays the rhythm (kick, bass, drums, percussion), Jonas the harmony with the chord progressions (column 1), the keys (column 2), the vibraphone (column 3), the flute (column 4; 5-7 empty for now) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Chapter (Jonas, column 8) switches between one chord (Vamp) and the progression chosen on Jonas 1 (Wechsel) at the next 4-bar phrase.

Every Launch Control XL 3 gets this full layout: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Tamb / Ride) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages. Two controllers: the control moved last wins.

Knob | Fader | Button | global (all modes) | unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Kick	2 Noise Pump	3 Sub	4 Bass	5 Clap	6 Hats / Shaker	7 Congas	8 Global
Row 1 Brightness	CC 13 **Brightness** 0 = round and tight ↔ extra click on top (lpf 4–16 kHz).	CC 14 **Brightness** soft whoosh ↔ airy hiss (lpf 2–14 kHz).	CC 15 **Brightness** 0 = sine with a few overtones (audible on small speakers) ↔ warm and full.	CC 16 **Brightness** dull ↔ bright (low-pass over each sound's own range); brighter also a little louder.	CC 17 **Brightness** natural ↔ sharp crack (lpf 3.5–14 kHz).	CC 18 **Brightness** soft hiss ↔ crisp and sharp (lpf 4–16 kHz).	CC 19 **Brightness** soft and woody ↔ crisp slap (lpf 1–12 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from outside the club.
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** dry ↔ far away (reverb + echo).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ a little room (reverb).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Punch** 0 = tight 909 kick ↔ harder: bigger pitch drop, more body.	CC 30 **Motion** still ↔ the filter breathes and the noise wanders left and right.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Sound** FM (Daft Punk) → M1 organ → warm analog.	CC 33 **Ghost notes** plain ↔ a quiet rim before beat 3 ↔ + small double taps.	CC 34 **Hats ↔ Shaker** 0 = 909 hats ↔ middle = both ↔ 1 = shaker (same rhythm).	CC 35 **Density** steady pattern ↔ + fingertip ghost notes.	CC 36 **Tension** build-up: echo grows, filters open (not hats, clap, shaker), from the middle a snare roll (clap fader), no further roll build-up above 80 %. 0 = release.
Fader Level	CC 5 **Level** 0 = gone. Four on the floor, tuned to A.	CC 6 **Level** noise that pumps with the kick.	CC 7 **Level** sub on the root, follows the chapter.	CC 8 **Level** bass line, follows the chords.	CC 9 **Level** clap on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** off-beat hat + swung 16ths.	CC 11 **Level** congas and bongos, in the background.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** 4/4 → a gap every 4th bar → a gap every 8th bar.	CC 38 **Change** pump → off-beat → 16ths.	CC 39 **Change** pump → off-beat → half bars.	CC 40 **Change** 6 lines: around the 1 + dead notes → dead notes → around the 1 → beat 4 open → pluck → Alright.	CC 41 **Change** 2 + 4 → with a pickup → a fill every 4th bar.	CC 42 **Change** off-beat → + swung 16ths → driving 16ths.	CC 43 **Change** pillow → rolling → latin.	CC 44 **Chapter** Vamp (Am9) ↔ Wechsel (col. 1 chords).

Button 2 Moment								
	CC 45 **Drop** kick, noise pump and sub pause while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 **Slide** every note bends up into its pitch while held.	CC 48 **Octave** one octave up while held.	CC 49 **Roll** snare roll, growing over the bar, while held.	CC 50 **Open** open hats on every 8th while held.	CC 51 **Fill** a conga run over the bar while held.	CC 52 **Break / Drop** 1st: kick, pump, sub, bass out (clap, hats, percussion stay). 2nd: all back on the one.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Harmony	2 Keys	3 Vibraphone	4 Flute	5	6	7	8 Global
Row 1 Brightness	CC 61 **Brightness** dull ↔ bright (low-pass over the sound's range).	CC 62 **Brightness** dull ↔ bright over each sound's own range (lpf from 250 Hz); top third: a presence peak; brighter also plays a little harder (±2 dB).	CC 63 **Brightness** dull ↔ bright (low-pass).	CC 64 **Brightness** dull ↔ bright (low-pass).	CC 65 —	CC 66 —	CC 67 —	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from outside the club.
Row 2 Space	CC 69 **Space** echo and room.	CC 70 **Space** 0 = dry; a 1/8 echo is there from the first turn (full at half), from about a third on the room joins (full at the top).	CC 71 **Soft** dry and short ↔ long notes, echo and room.	CC 72 **Space** echo and room (a little at 0).	CC 73 —	CC 74 —	CC 75 —	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Strings ↔ B3** strings → both → B3 alone.	CC 78 **Length** 0 = short stab ↔ hits ring four times longer.	CC 79 **Complexity** core notes → figure → fills → doubles.	CC 80 **Playful** core motif → + neighbour notes → + a short trill.	CC 81 —	CC 82 —	CC 83 —	CC 36 **Tension** build-up: echo grows, filters open (not hats, clap, shaker), from the middle a snare roll (clap fader), no further roll build-up above 80 %. 0 = release.
Fader Level	CC 53 **Level** held chords, follow the progression.	CC 54 **Level** keys: Steinway (VCSL) and Rhodes Mark I (jRhodes3d), organs, mallets.	CC 55 **Level** vibraphone phrases, follow the chords.	CC 56 **Level** flute melody from real flute notes, follows the chords.	CC 57 —	CC 58 —	CC 59 —	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 85 **Progression** next of 10, at the next 8-bar phrase (plays in Wechsel).	CC 86 **Change** 8 stab rhythms on Am9 (chain, shifted, pairs, 3-3-2, two Kerri, two overlays), then 6 riffs with their own chords (Kerri video, Checkmate, Turn Off, Atmosphere, Chicago, Retro-Disco): for those Chapter on Vamp.	CC 87 **Phrase** off-beat → tresillo → echo of the call, next bar.	CC 88 **Motif** hopping → call and answer → turn, next bar.	CC 89 —	CC 90 —	CC 91 —	CC 44 **Chapter** Vamp (Am9) ↔ Wechsel (col. 1 chords).
Button 2 Moment	CC 93 **Echo throw** held: long dotted-8th echo.	CC 94 **Sound** on / off: knobs = sound mix (piano → Rhodes, B3 → M1, vibes → marimba); fader = overtones.	CC 95 **Echo throw** held: long dotted-8th echo.	CC 96 **Echo throw** held: long dotted-8th echo.	CC 97 —	CC 98 —	CC 99 —	CC 52 **Break / Drop** 1st: kick, pump, sub, bass out (clap, hats, percussion stay). 2nd: all back on the one.

Guide

Building it up

One layer after the other, not all at once: drums (kick, hats, clap), then bass and sub, then the keys, then percussion (congas, tambourine). Start in Vamp.

Harmony

Button 1 of column 1 picks the progression (at the next 8-bar phrase); it plays when Chapter is Wechsel. Row 3 fades strings → strings + B3 → B3.

Keys

1:1 from the keys lab (round 19, column 2): brightness, space, length; button 1 = stab rhythm (8); button 2 = sound: the knobs mix the sound (piano → Rhodes, organ B3 → M1, vibraphone → marimba), the fader sets how strongly the overtones follow the accent.

Break and drop

Jonas presses Break: kick, noise pump, sub and bass go out at the next bar; clap, hats, percussion and tambourine keep the build-up going. Jojo holds the riser (noise pump, button 2). Jonas switches Chapter to Wechsel and presses Break again: everything is back on the one, now with the progression.

Every position sounds good

All knobs at 0 is dry, close and clear, as the track is meant to be. Space adds room, it does not repair. Every column has its own fader: each layer can be muted on its own.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.

Playing together

Both Launch Controls have the full layout and steer the same sounds: whoever moves a control last sets its value, a button press counts from either. Agree who plays which page.