Launch Control XL 3 — Track 007 — ambient moods (one controller)

Dreamy ambient on D, about 70 BPM. Jojo plays the foundation (heartbeat, drone, bass and soft clicks), Jonas the colour (pad, chords, melodies) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar, 8 per stem), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up.

Only Jonas' controller: Mode 16 = Jonas (colour), Mode 2 = Jojo (foundation, columns 1–7; Jojo's column 8 (Crackle) stays off). Column 8 is the same global column on both pages.

Knob | Fader | Button | global (all modes) | unused

Jonas — Colour (chords + melodies) · column 8 = global

	1 Pad	2 Chords	3 Music Box	4 Whale	5 Choir	6 Glitter	7 Shimmer	8 Global
Row 1 Brightness	CC 13 **Brightness** muffled ↔ open and airy (lpf 300–8000 Hz).	CC 14 **Brightness** warm ↔ bright, glassy (lpf 400–10000 Hz).	CC 15 **Brightness** soft plucks ↔ sharp, sparkling (lpf 1.5–14 kHz).	CC 16 **Brightness** soft and round ↔ clear and nasal (lpf 300–6000 Hz).	CC 17 **Brightness** hushed ↔ clear (lpf 500–10000 Hz).	CC 18 **Brightness** soft glow ↔ glittering (lpf 2–16 kHz).	CC 19 **Brightness** dark whoosh ↔ bright shimmer (lpf 1.5–14 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: distant, under water.
Row 2 Space	CC 21 **Space** dry and close ↔ far away in a big room (reverb + echo).	CC 22 **Space** dry ↔ far away (reverb + echo).	CC 23 **Space** dry ↔ far away (reverb + echo).	CC 24 **Space** dry ↔ far away (reverb + echo).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Swell** 0 = still, held chords. Up = the chord is re-struck every half bar and breathes in and out.	CC 30 **Length** long ringing chords ↔ short, choppy stabs.	CC 31 **Density** a few notes of the tune ↔ every 8th plays.	CC 32 **Glide** how far each call slides into its note: 0 = ±2 semitones, 1 = ±12 (deep, eerie bends).	CC 33 **Voices** 0 = one voice, 0.5 = + a third above, 1 = + a fifth: three-part harmony.	CC 34 **Density** a drop now and then (~1 per bar) ↔ a sparkling rain (~70 % of the 16ths).	CC 35 **Amount** subtle (one tone) ↔ wild (a bell-like chord with long echoes).	CC 36 **Tension** 0–0.5: echo grows on all melodic stems, filters open. 0.5–1: + slow tape wobble on the long sounds. Back to 0 = release.
Fader Level	CC 5 **Level** long floating chords.	CC 6 **Level** soft chord pings over the pad (same chords as the pad).	CC 7 **Level** slow music box.	CC 8 **Level** whale calls, about two in three bars.	CC 9 **Level** choir voices.	CC 10 **Level** glitter drops.	CC 11 **Level** shimmer swells, a new one every 2 bars.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** next of 8 chord progressions (chords follow).	CC 38 **Change** next of 8 rhythms (3-in-8, 5-in-8, …).	CC 39 **Change** next of 8 random note choices and octave leaps.	CC 40 **Change** next of 8 random call sequences.	CC 41 **Change** next of 8 random melodies.	CC 42 **Change** next of 8 random drop patterns.	CC 43 **Change** next of 8 random note sequences.	CC 44 **Chapter** lydian → dorian → whole tone, at the next bar.
Button 2 Moment	CC 45 **Freeze** holds the current chord while held.	CC 46 **Stab** chord stabs on every 8th while held.	CC 47 **Octave** one octave up while held.	CC 48 **Echo throw** long echo on the calls while held.	CC 49 **Full choir** all three voices while held.	CC 50 **Burst** a rain of sparkles while held.	CC 51 **Rise** while held, 16th pings rise in volume over 2 bars.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Mode 2 — Jojo: Foundation (beat + bass) · CC + 48

	1 Pulse	2 Sea / Wind	3 Drone	4 Bass	5 Rim	6 Ticks	7 Wood / Drops	8 Global
Row 1 Brightness	CC 61 **Brightness** dull thump ↔ clicky attack (lpf 180–1500 Hz).	CC 62 **Brightness** deep rumble ↔ airy hiss (lpf 200–12000 Hz, moves with the waves).	CC 63 **Brightness** pure and dark ↔ open, the overtones come through (lpf 120–4000 Hz).	CC 64 **Brightness** round and dark ↔ the saw's buzz comes through (lpf 80–2000 Hz).	CC 65 **Brightness** soft and far ↔ sharp crack (lpf 1.2–12 kHz).	CC 66 **Brightness** soft tick ↔ crisp and sharp (lpf 3–16 kHz).	CC 67 **Brightness** woody (pure sine blip) ↔ metallic (FM).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: distant, under water.
Row 2 Space	CC 69 **Space** dry and close ↔ far away in a big room (reverb).	CC 70 **Space** dry ↔ far away (reverb).	CC 71 **Space** dry ↔ far away (reverb).	CC 72 **Space** dry ↔ far away (reverb).	CC 73 **Space** dry ↔ far away (reverb + echo).	CC 74 **Space** dry ↔ far away (reverb + echo).	CC 75 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Drive** three steps: soft sine thump → synth kick → firm kick with more click.	CC 78 **Sea ↔ Wind** 0 = brown-noise waves rolling in, 0.5 = both, 1 = only whistling wind gusts.	CC 79 **Beating** 0 = pure sines. Up = a detuned saw copy fades in, the two beat against each other (slow “wah-wah”).	CC 80 **Groove** 0 = a soft swell every bar. Up to 0.5 a 3-3-2 pulse fades in, at 1 only the pulse.	CC 81 **Ghost notes** plain ↔ extra quiet clicks in between.	CC 82 **Density** 8ths ↔ + 16ths ↔ + little flutters.	CC 83 **Density** a click now and then ↔ a busy pattern.	CC 36 **Tension** 0–0.5: echo grows on all melodic stems, filters open. 0.5–1: + slow tape wobble on the long sounds. Back to 0 = release.
Fader Level	CC 53 **Level** 0 = gone. A heartbeat thump on D.	CC 54 **Level** sea and wind. Keeps playing in the break.	CC 55 **Level** slow drone chords on D.	CC 56 **Level** slow bass swells.	CC 57 **Level** soft rim click on 2 and 4.	CC 58 **Level** clock ticks.	CC 59 **Level** wood clicks and drops.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 85 **Change** heartbeat → quarters → half notes.	CC 86 **Change** next of 8 random wave / gust patterns.	CC 87 **Change** next of 8 drone chords per chapter (D–A, D–A–E, …).	CC 88 **Change** next of 8 bass lines (a note every 2 bars).	CC 89 **Change** next of 8 click patterns.	CC 90 **Change** next of 8 random accent / 16th patterns.	CC 91 **Change** next of 8 random patterns.	CC 44 **Chapter** lydian → dorian → whole tone, at the next bar.
Button 2 Moment	CC 93 **Drop out** pulse pauses while held.	CC 94 **Riser** a noise sweep rises over 2 bars while held.	CC 95 —	CC 96 **Octave** one octave up while held.	CC 97 **Roll** 16th roll, growing over the bar, while held.	CC 98 **Open** ticks ring long while held.	CC 99 **Fill** almost every 16th plays while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Playing together

Jojo builds the floor: drone and bass first, then the heartbeat, then the small clicks. Jonas colours it: pad and chords, then whale, choir and the sparkles on top.

Jonas' column 8 acts on everything: Fog and Tension darken or open all filters, Room drowns everything in reverb, Chapter changes the key colour for both players at the next bar.

Break: one press takes out the beat (pulse, bass, rim, ticks, wood) at the next bar; drone, crackle, sea and all of Jonas' sounds keep floating. The second press brings the beat back on the one.

Every position sounds good

No filter closes completely, and space 0 is dry but never silent. Row 2 at about the middle gives each sound the room it had in the original track.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 2, switch to Mode 16, add colour, use column 8 for the drop.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.