Launch Control XL 3 — Track 007 (ambient moods)

Dreamy ambient on D, about 70 BPM. Three moods on the global button 2, switching at the next bar: lydian (floating, bright), dorian (melancholic, misty), whole tone (strange, no key).

Every column: HPF, LPF, character, level, button 1 = next random variation (8 per stem). Column 1, knob 1 = level of a soft heartbeat thump on D, independent of the drone fader (pulse without drone works).

LPF knobs at 0 are almost closed: open row 2 first. The global knobs at 0 are neutral (dry, clear, no echo).

The status box at the bottom right of the Strudel page shows mood, pulse rhythm and each stem's variation. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Knob Fader Button unused

Mode 16 — Ambient

	1 Drone + Pulse	2 Pad	3 Glitter	4 Sea / Wind	5 Whale	6 Choir	7 Music Box	8 Global
Row 1 HPF	CC 13 **Pulse** level of a soft kick on D, 0 = off. Plays without the drone fader too.	CC 14 **HPF** 40–1500 Hz	CC 15 **HPF** 200–4000 Hz	CC 16 **HPF** 20–2000 Hz	CC 17 **HPF** 20–800 Hz	CC 18 **HPF** 80–2000 Hz	CC 19 **HPF** 100–3000 Hz	CC 20 **Space** 0 = each stem's own reverb, 1 = everything drowns in reverb.
Row 2 LPF	CC 21 **LPF** 80–4000 Hz	CC 22 **LPF** 150–8000 Hz	CC 23 **LPF** 1–16 kHz	CC 24 **LPF** 200–12000 Hz (moves with the waves)	CC 25 **LPF** 150–6000 Hz	CC 26 **LPF** 300–10000 Hz	CC 27 **LPF** 1–14 kHz	CC 28 **Fog** 0 = clear, 1 = every stem's LPF pulled down to ~6 %: distant, under water.
Row 3 Character	CC 29 **Beating** 0 = pure sines. Up = a detuned saw copy fades in, the two beat against each other (slow “wah-wah”).	CC 30 **Shimmer** 0 = only the soft chord swells. Up = the chord an octave higher pings in a 3-in-8 rhythm with echoes.	CC 31 **Density** 0 = a drop now and then (~1 per bar), 1 = a sparkling rain (~70 % of the 16ths).	CC 32 **Sea ↔ Wind** 0 = brown-noise waves rolling in, 0.5 = both, 1 = only whistling wind gusts.	CC 33 **Glide** how far each call slides into its note: 0 = ±2 semitones, 1 = ±12 (deep, eerie bends).	CC 34 **Voices** 0 = one voice, 0.5 = + a third above, 1 = + a fifth: three-part harmony.	CC 35 **Density** 0 = a few notes of the tune, 1 = every 8th plays.	CC 36 **Dream** 0–0.5: echo on all stems (not the pulse). 0.5–1: + a slow, gentle wobble on drone, pad, choir.
Fader Level	CC 5 **Level** drone, 0–1 (not the pulse)	CC 6 **Level** 0–1	CC 7 **Level** 0–1	CC 8 **Level** 0–1	CC 9 **Level** 0–1	CC 10 **Level** 0–1	CC 11 **Level** 0–1	CC 12 **Master Level** volume of everything.
Button 1 Variation	CC 37 **Variation** next of 8 drone chords per mood (D-A, D-A-E, …).	CC 38 **Variation** next of 8 random chord progressions.	CC 39 **Variation** next of 8 random drop patterns.	CC 40 **Variation** next of 8 random wave / gust patterns.	CC 41 **Variation** next of 8 random call sequences.	CC 42 **Variation** next of 8 random melodies.	CC 43 **Variation** next of 8 random note choices and octave leaps.	CC 44 **Re-roll all** all stems: next variation at once.
Button 2 Pulse / Mood	CC 45 **Pulse rhythm** heartbeat → quarters → half notes.	CC 46 **Pulse softness** soft → medium → hard (all rhythms). Starts soft.	CC 47 —	CC 48 —	CC 49 —	CC 50 —	CC 51 —	CC 52 **Mood** lydian → dorian → whole tone, at the next bar.