Launch Control XL 3 — Track 009 — dry house (two controllers)

Dry, happy oldschool house in A minor, 124 BPM: short sounds, one piano hook on the off-beats. Jojo plays the rhythm (kick, bass, drums, percussion), Jonas the melody (pad, piano, riff, organ, vocal chops, orchestra hit, Rhodes) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Chapter (Jonas, column 8) switches between one chord (Vamp) and two chords (Wechsel) at the next 4-bar phrase.

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Knob | Fader | Button | global (all modes) | unused

Jojo — Rhythm (beat + bass)

	1 Kick	2 Noise Pump	3 Sub	4 Bass	5 Clap	6 Hats / Shaker	7 Congas	8 Tamb / Ride
Row 1 Brightness	CC 13 **Brightness** 0 = round and tight ↔ extra click on top (lpf 4–16 kHz).	CC 14 **Brightness** soft whoosh ↔ airy hiss (lpf 2–14 kHz).	CC 15 **Brightness** 0 = sine with a few overtones (audible on small speakers) ↔ warm and full.	CC 16 **Brightness** round ↔ a clear, buzzing edge (lpf 700–5000 Hz).	CC 17 **Brightness** natural ↔ sharp crack (lpf 3.5–14 kHz).	CC 18 **Brightness** soft hiss ↔ crisp and sharp (lpf 4–16 kHz).	CC 19 **Brightness** soft and woody ↔ crisp slap (lpf 1–12 kHz).	CC 20 **Brightness** soft shimmer ↔ bright sizzle (lpf 4.5–16 kHz).
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** dry ↔ far away (reverb + echo).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ a little room (reverb).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Space** dry ↔ far away (reverb + echo).
Row 3 Character	CC 29 **Punch** 0 = tight 909 kick ↔ harder: bigger pitch drop, more body.	CC 30 **Motion** still ↔ the filter breathes and the noise wanders left and right.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Groove** the line as it is ↔ extra ghost notes rolling in between.	CC 33 **Ghost notes** plain ↔ a quiet rim before beat 3 ↔ + small double taps.	CC 34 **Hats ↔ Shaker** 0 = 909 hats ↔ middle = both ↔ 1 = shaker (same rhythm).	CC 35 **Density** steady pattern ↔ + fingertip ghost notes.	CC 36 **Swing** straight ↔ swung, lazy (the in-between 16ths come late).
Fader Level	CC 5 **Level** 0 = gone. Four on the floor, tuned to A.	CC 6 **Level** noise that pumps with the kick.	CC 7 **Level** sub on the root, follows the chapter.	CC 8 **Level** bass line, follows the chapter.	CC 9 **Level** clap on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** off-beat hat + swung 16ths.	CC 11 **Level** congas and bongos, in the background.	CC 12 **Level** tambourine / ride.
Button 1 Change	CC 37 **Change** 4/4 → a gap every 4th bar → a gap every 8th bar.	CC 38 **Change** pump → off-beat → 16ths.	CC 39 **Change** pump → off-beat → half bars.	CC 40 **Change** syncopated → two-bar melody → off-beat.	CC 41 **Change** 2 + 4 → with a pickup → a fill every 4th bar.	CC 42 **Change** off-beat → + swung 16ths → driving 16ths.	CC 43 **Change** pillow → rolling → latin.	CC 44 **Change** tambourine → ride → both.
Button 2 Moment	CC 45 **Drop** kick, noise pump and sub pause while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 **Slide** every note bends up into its pitch while held.	CC 48 **Octave** one octave up while held.	CC 49 **Roll** snare roll, growing over the bar, while held.	CC 50 **Open** open hats on every 8th while held.	CC 51 **Fill** a conga run over the bar while held.	CC 52 **Double** double time while held.

Jonas — Melody (piano + colour) · column 8 = global

	1 Pad	2 Piano	3 Piano Riff	4 Organ	5 Vocal Chops	6 Orch Hit	7 Rhodes	8 Global
Row 1 Brightness	CC 13 **Brightness** soft ↔ open and bright (lpf 1.2–9 kHz).	CC 14 **Brightness** clear ↔ glassy and bright (lpf 5–18 kHz). Never muffled.	CC 15 **Brightness** clear ↔ glassy and bright (lpf 5–18 kHz).	CC 16 **Brightness** round ↔ bright and buzzing (lpf 1.5–12 kHz).	CC 17 **Brightness** hushed ↔ clear (lpf 1.5–12 kHz).	CC 18 **Brightness** dull ↔ bright, brassy (lpf 1.5–14 kHz).	CC 19 **Brightness** warm ↔ bell-like tine (lpf 2–12 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from outside the club.
Row 2 Space	CC 21 **Space** dry ↔ a big hall (reverb + echo).	CC 22 **Space** dry ↔ the echoes repeat into the room.	CC 23 **Space** dry ↔ the echoes repeat into the room.	CC 24 **Space** dry ↔ far away (reverb + echo).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Motion** 0 = still ↔ the filter breathes slowly over 4 bars.	CC 30 **Voicing** 0 = four close notes ↔ + top note an octave up ↔ + the root in the left hand.	CC 31 **Octaves** single notes ↔ played in octaves (the note an octave lower joins).	CC 32 **Length** short, detached notes ↔ held, singing notes.	CC 33 **Voices** one voice ↔ + a third below ↔ + the octave above: a chord.	CC 34 **Chord** one hit on the root ↔ + fifth and octave: a big chord.	CC 35 **Length** short chords ↔ held over the bar.	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 5 **Level** pad on the chapter's chord. Keeps playing in the break.	CC 6 **Level** piano stabs on the chapter's chord.	CC 7 **Level** piano riff.	CC 8 **Level** organ line.	CC 9 **Level** vocal chops, every few bars.	CC 10 **Level** orchestra hit.	CC 11 **Level** Rhodes chords. Keeps playing in the break.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** full chord → only the top (thin, high) → low and wide.	CC 38 **Change** stab → push → ghost notes → call and answer.	CC 39 **Change** repeated note → rising line → call and answer.	CC 40 **Change** answer in bar 2 → falling hymn → short call.	CC 41 **Change** every 2nd bar → every 4th bar → end of the phrase.	CC 42 **Change** phrase start → a pair every 2nd bar → pickup.	CC 43 **Change** on 1 → on the off-beats → 1 + a late answer.	CC 44 **Chapter** Vamp ↔ Wechsel, at the next phrase.
Button 2 Moment	CC 45 **Freeze** holds the current chord while held, for everybody.	CC 46 **Echo** a short echo on the stabs while held.	CC 47 **Octave** one octave up while held.	CC 48 **Echo throw** long echo on the organ while held.	CC 49 **Echo throw** long echo on the chops while held.	CC 50 **Hits** a hit on every beat while held.	CC 51 **Swell** the chord swells in slowly while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Building it up

One layer after the other, not all at once: drums (kick, hats, clap), then bass and sub, then the piano hook, then percussion (congas, tambourine). Start in Vamp.

The hook

The piano is the one melody. Let it run, change it only a little: button 1 (stab → push → ghosts → answer), row 3 (bigger voicing). Riff, organ and Rhodes are alternatives for other sections, not a second layer on top.

Break and drop

Jonas presses Break: the whole rhythm goes out at the next bar, only piano or pad keep playing (pull the rest down). Jojo holds the riser (noise pump, button 2). Jonas switches Chapter to Wechsel and presses Break again: everything is back on the one, now with two chords.

Every position sounds good

All knobs at 0 is dry, close and clear, as the track is meant to be. Space adds room, it does not repair. Every column has its own fader: each layer can be muted on its own.