Launch Control XL 3 — Track 009 — house (two controllers)

Happy, jazzy, dry house in A minor, 124 BPM. Jojo plays the rhythm (kick, bass, drums, percussion), Jonas the harmony with the chord progressions (column 1), the keys (column 2), the vibraphone (column 3; 4-7 empty for now) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Chapter (Jonas, column 8) switches between one chord (Vamp) and the progression chosen on Jonas 1 (Wechsel) at the next 4-bar phrase.

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Knob | Fader | Button | global (all modes) | unused

Jojo — Rhythm (beat + bass)

	1 Kick	2 Noise Pump	3 Sub	4 Bass	5 Clap	6 Hats / Shaker	7 Congas	8 Tamb / Ride
Row 1 Brightness	CC 13 **Brightness** 0 = round and tight ↔ extra click on top (lpf 4–16 kHz).	CC 14 **Brightness** soft whoosh ↔ airy hiss (lpf 2–14 kHz).	CC 15 **Brightness** 0 = sine with a few overtones (audible on small speakers) ↔ warm and full.	CC 16 **Brightness** round ↔ a clear, buzzing edge (lpf 700–5000 Hz).	CC 17 **Brightness** natural ↔ sharp crack (lpf 3.5–14 kHz).	CC 18 **Brightness** soft hiss ↔ crisp and sharp (lpf 4–16 kHz).	CC 19 **Brightness** soft and woody ↔ crisp slap (lpf 1–12 kHz).	CC 20 **Brightness** soft shimmer ↔ bright sizzle (lpf 4.5–16 kHz).
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** dry ↔ far away (reverb + echo).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ a little room (reverb).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Space** dry ↔ far away (reverb + echo).
Row 3 Character	CC 29 **Punch** 0 = tight 909 kick ↔ harder: bigger pitch drop, more body.	CC 30 **Motion** still ↔ the filter breathes and the noise wanders left and right.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Groove** the line as it is ↔ random ghost notes (root, fifth, seventh) rolling in between.	CC 33 **Ghost notes** plain ↔ a quiet rim before beat 3 ↔ + small double taps.	CC 34 **Hats ↔ Shaker** 0 = 909 hats ↔ middle = both ↔ 1 = shaker (same rhythm).	CC 35 **Density** steady pattern ↔ + fingertip ghost notes.	CC 36 **Swing** straight ↔ swung, lazy (the in-between 16ths come late).
Fader Level	CC 5 **Level** 0 = gone. Four on the floor, tuned to A.	CC 6 **Level** noise that pumps with the kick.	CC 7 **Level** sub on the root, follows the chapter.	CC 8 **Level** bass line, follows the chapter.	CC 9 **Level** clap on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** off-beat hat + swung 16ths.	CC 11 **Level** congas and bongos, in the background.	CC 12 **Level** tambourine / ride.
Button 1 Change	CC 37 **Change** 4/4 → a gap every 4th bar → a gap every 8th bar.	CC 38 **Change** pump → off-beat → 16ths.	CC 39 **Change** pump → off-beat → half bars.	CC 40 **Change** syncopated → two-bar melody → off-beat.	CC 41 **Change** 2 + 4 → with a pickup → a fill every 4th bar.	CC 42 **Change** off-beat → + swung 16ths → driving 16ths.	CC 43 **Change** pillow → rolling → latin.	CC 44 **Change** tambourine → ride → both.
Button 2 Moment	CC 45 **Drop** kick, noise pump and sub pause while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 **Slide** every note bends up into its pitch while held.	CC 48 **Octave** one octave up while held.	CC 49 **Roll** snare roll, growing over the bar, while held.	CC 50 **Open** open hats on every 8th while held.	CC 51 **Fill** a conga run over the bar while held.	CC 52 **Double** double time while held.

Jonas — Melody (keys + top voices) · column 8 = global

	1 Harmony	2 Keys	3 Vibraphone	4	5	6	7	8 Global
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (low-pass over the sound's range).	CC 14 **Brightness** dull ↔ bright over each sound's own range (lpf from 250 Hz); top third: a presence peak; brighter also plays a little harder (±2 dB).	CC 15 **Brightness** dull ↔ bright (low-pass).	CC 16 —	CC 17 —	CC 18 —	CC 19 —	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from outside the club.
Row 2 Space	CC 21 **Space** echo and room.	CC 22 **Space** 0 = dry; a 1/8 echo is there from the first turn (full at half), from about a third on the room joins (full at the top).	CC 23 **Soft** dry and short ↔ long notes, echo and room.	CC 24 —	CC 25 —	CC 26 —	CC 27 —	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Strings ↔ B3** strings → both → B3 alone.	CC 30 **Length** 0 = short stab ↔ hits ring four times longer.	CC 31 **Complexity** core notes → figure → fills → doubles.	CC 32 —	CC 33 —	CC 34 —	CC 35 —	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 5 **Level** held chords, follow the progression.	CC 6 **Level** keys: Steinway (VCSL) and Rhodes Mark I (jRhodes3d), organs, mallets.	CC 7 **Level** vibraphone phrases, follow the chords.	CC 8 —	CC 9 —	CC 10 —	CC 11 —	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Progression** next of 10, at the next 8-bar phrase (plays in Wechsel).	CC 38 **Change** 8 stab rhythms (chain, shifted, pairs, 3-3-2, two Kerri, two overlays).	CC 39 **Phrase** off-beat → tresillo → echo of the call, next bar.	CC 40 —	CC 41 —	CC 42 —	CC 43 —	CC 44 **Chapter** Vamp (Am9) ↔ Wechsel (col. 1 chords).
Button 2 Moment	CC 45 **Echo throw** held: long dotted-8th echo.	CC 46 **Sound** on / off: knobs = sound mix (piano → Rhodes, B3 → M1, vibes → marimba); fader = overtones.	CC 47 **Echo throw** held: long dotted-8th echo.	CC 48 —	CC 49 —	CC 50 —	CC 51 —	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Building it up

One layer after the other, not all at once: drums (kick, hats, clap), then bass and sub, then the keys, then percussion (congas, tambourine). Start in Vamp.

Harmony

Button 1 of column 1 picks the progression (at the next 8-bar phrase); it plays when Chapter is Wechsel. Row 3 fades strings → strings + B3 → B3.

Keys

1:1 from the keys lab (round 19, column 2): brightness, space, length; button 1 = stab rhythm (8); button 2 = sound: the knobs mix the sound (piano → Rhodes, organ B3 → M1, vibraphone → marimba), the fader sets how strongly the overtones follow the accent.

Break and drop

Jonas presses Break: the whole rhythm goes out at the next bar, only the keys keep playing. Jojo holds the riser (noise pump, button 2). Jonas switches Chapter to Wechsel and presses Break again: everything is back on the one, now with the progression.

Every position sounds good

All knobs at 0 is dry, close and clear, as the track is meant to be. Space adds room, it does not repair. Every column has its own fader: each layer can be muted on its own.