Launch Control XL 3 — House Keys Lab 25 (lab/keys, round 25 for 009: under a riff — bass and pad follow it, a pedal on A, or no pad)

Round 25: Mode 2, column 7, button 1 = what bass and pad do while a riff leads: follow → pedal A + Am9 → bass follows, no pad → pedal A, no pad (at the next phrase).

Whoever was chosen last leads the chords: a riff column raised from 0, or the monotone keys (column 2) / a new progression (Mode 2, column 1, button 1). Bass and harmony pad follow the leader.

A switch takes over at the next 4-bar phrase; the new leader starts from its first bar. Only the leading keys column sounds; the monotone keys sound while the progression leads.

Knob Fader Button unused

Mode 16 — Keys

	1 Kerri video	2 Monoton (009)	3 Checkmate	4 Turn Off The Lights	5 Atmosphere	6 Chicago spread	7 Retro disco (16)	8
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright over the sound's own range; brighter also plays a little harder.	CC 14 **Brightness** as 1 Kerri video	CC 15 **Brightness** as 1 Kerri video	CC 16 **Brightness** as 1 Kerri video	CC 17 **Brightness** as 1 Kerri video	CC 18 **Brightness** as 1 Kerri video	CC 19 **Brightness** as 1 Kerri video	CC 20 —
Row 2 Space	CC 21 **Space** 0 = dry; a 1/8 echo first, then the room.	CC 22 **Space** as 1 Kerri video	CC 23 **Space** as 1 Kerri video	CC 24 **Space** as 1 Kerri video	CC 25 **Space** as 1 Kerri video	CC 26 **Space** as 1 Kerri video	CC 27 **Space** as 1 Kerri video	CC 28 —
Row 3 Length	CC 29 **Length** 0 = short stab ↔ hits ring four times longer.	CC 30 **Length** as 1 Kerri video	CC 31 **Length** as 1 Kerri video	CC 32 **Length** as 1 Kerri video	CC 33 **Length** as 1 Kerri video	CC 34 **Length** as 1 Kerri video	CC 35 **Length** as 1 Kerri video	CC 36 —
Fader Level	CC 5 **Level** raised from 0: this column leads at the next phrase (riff: its chords; column 2: the progression).	CC 6 **Level** as 1 Kerri video	CC 7 **Level** as 1 Kerri video	CC 8 **Level** as 1 Kerri video	CC 9 **Level** as 1 Kerri video	CC 10 **Level** as 1 Kerri video	CC 11 **Level** as 1 Kerri video	CC 12 —
Button 1 Rhythm	CC 37 **Rhythm** the video's rhythm → then the 8 rhythms of 009.	CC 38 **Rhythm** 8 rhythms of 009 on Am9: chain → shifted → pairs → 3-3-2 → Kerri syncope → Kerri riff → two overlays.	CC 39 **Rhythm** (one rhythm: the riff's own)	CC 40 **Rhythm** as 3 Checkmate	CC 41 **Rhythm** as 3 Checkmate	CC 42 **Rhythm** as 3 Checkmate	CC 43 **Rhythm** as 3 Checkmate	CC 44 —
Button 2 Sound	CC 45 **Sound** held: knobs = sound mix (piano → Rhodes, B3 → M1, vibes → marimba); fader = overtones.	CC 46 **Sound** as 1 Kerri video	CC 47 **Sound** as 1 Kerri video	CC 48 **Sound** as 1 Kerri video	CC 49 **Sound** as 1 Kerri video	CC 50 **Sound** as 1 Kerri video	CC 51 **Sound** as 1 Kerri video	CC 52 —

Mode 2 — Harmony, drums, bass

	1 Harmony	2	3	4	5	6 Drums	7 Bass	8
Row 1	CC 61 **Brightness** dull ↔ bright (low-pass 400–6000 Hz).	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 **Space** echo and room.	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 **Strings ↔ B3** strings → both → B3 alone.	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 **Level** held chords of the leader (riff or progression), as track 009's Jonas 1.	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the root of the leader's chord.	CC 60 —
Buttons 1	CC 85 **Progression** next of 10 (track 009); the progression leads again from the next phrase.	CC 86 —	CC 87 —	CC 88 —	CC 89 —	CC 90 —	CC 91 **Under a riff** follow → pedal A + Am9 → bass follows, no pad → pedal A, no pad (next phrase).	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 **Drums out** keys and bass alone while held.	CC 99 —	CC 100 —

Guide

What to listen for

Does the bass on the riff's roots make the riff stronger? Does the held pad under a riff help or get in the way (Checkmate, Turn Off The Lights)? Is the handover at the phrase musical?

Try

Raise column 2 (monotone keys) and the pad (Mode 2 fader 1), pick progressions with Mode 2 button 1. Then raise a riff column: at the next phrase it takes over, bass and pad move to its chords. Pull it down: the progression comes back.