Launch Control XL 3 — Track 008 — groove techno

Groove techno on F minor, 140 BPM. Jojo plays the foundation (kick, bass, drums), Jonas the colour (pads, stab, percussion) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Jonas' pad button 1 changes the chords, and Jojo's sub and bassline follow.

Every Launch Control XL 3 gets this full layout: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Ride) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages. Two controllers: the control moved last wins.

Knob | Fader | Button | global (all modes) | unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Kick	2 Rumble	3 Sub	4 Bassline	5 Clap	6 Hats	7 Percussion	8 Global
Row 1 Brightness	CC 13 **Brightness** 0 = round but clear ↔ clicky attack (lpf 900–9000 Hz).	CC 14 **Brightness** 0 = warm rumble ↔ more of the kick's body in the tail (lpf 250–1800 Hz).	CC 15 **Brightness** 0 = sine with a few overtones (audible on small speakers) ↔ warm and full.	CC 16 **Brightness** dark and dull ↔ biting (lpf 200–2000 Hz, the note envelope opens above it).	CC 17 **Brightness** 0 = bright (round 8: where 90 % was) ↔ sharp crack (lpf 9.8–12 kHz).	CC 18 **Brightness** crisp ↔ sizzling (lpf 9–18 kHz).	CC 19 **Brightness** 0 = where 65 % was (round 8) ↔ metallic (FM and lpf 4.2–12 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from the room next door.
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** short rumble ↔ a long dark cloud (reverb never fully off: the reverb is the sound).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ a little room (reverb).	CC 25 **Space** dry ↔ far away (reverb).	CC 26 **Space** dry ↔ far away (reverb).	CC 27 **Space** dry ↔ far away (reverb).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Punch** 0 = really soft thump, middle = round kick, 1 = hard and punchy.	CC 30 **Motion** still ↔ the filter breathes and the rumble echoes in 16ths.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Groove** the line as written ↔ quiet ghost 16ths roll in the gaps.	CC 33 **Ghost notes** plain ↔ a quiet clap before beat 3 ↔ + small double taps.	CC 34 **Density** the pattern as it is ↔ + quiet 16ths ↔ + little 32nd rolls.	CC 35 **Density** steady pattern ↔ + fingertip ghost notes ↔ + little rolls.	CC 36 **Tension** build-up: echo grows (answer, sequence), filters open, only in the last fifth a snare roll (clap fader). 0 = release.
Fader Level	CC 5 **Level** 0 = gone. Kick on every beat, tuned to C (fifth of F).	CC 6 **Level** rumble under the kick, same pitch (C).	CC 7 **Level** pumping sub, follows Jonas' chords.	CC 8 **Level** dark rolling bass, follows Jonas' chords.	CC 9 **Level** clap on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** open hats. Keep playing in the break.	CC 11 **Level** bongos and rimshot. Keep playing in the break.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Double time** 8 kicks per bar instead of 4 while held.	CC 38 **Change** 3rd + 4th 16th → 2nd–4th → only the 3rd.	CC 39 **Change** pump → fifth on beat 4 → syncopated.	CC 40 **Change** rolling → acid → stomp.	CC 41 **Change** short clap → with pickup → full drop clap (tail + double).	CC 42 **Change** open off-beat → + closed 16ths → driving.	CC 43 **Change** pillow → gallop → 3-3-2.	CC 44 **Drop fill** hold while the beat is out: 4-bar fill from the next bar, the beat is back after the 16th beat. Let go = stop.
Button 2 Moment	CC 45 **Drop out** kick pauses while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 **Slide** every note bends up into its pitch while held.	CC 48 **Octave** one octave up while held.	CC 49 **Swell** snare swell over 4 bars while held.	CC 50 **Long** the open hats ring longer, on every 8th, while held.	CC 51 **Fill** a bongo run down over the bar while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Pad	2 Techno Pad	3 Sequence	4 Stab	5 Answer	6 Dark Perc	7 FX / Breath	8 Global
Row 1 Brightness	CC 61 **Brightness** muffled ↔ open and airy (lpf 250–6000 Hz).	CC 62 **Brightness** dark and muffled ↔ open and wide (lpf 300–4000 Hz, drifting slowly).	CC 63 **Brightness** soft wooden mallet ↔ sharp, glassy (lpf 1.5–12 kHz, more FM).	CC 64 **Brightness** dark, muted stab ↔ open and biting (lpf 400–4000 Hz, drifting slowly).	CC 65 **Brightness** soft ↔ clear and bright (lpf 2–12 kHz).	CC 66 **Brightness** dull ↔ bright and biting (lpf 5–18 kHz).	CC 67 **Brightness** dark whoosh ↔ bright hiss (lpf 1.5–14 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from the room next door.
Row 2 Space	CC 69 **Space** dry and close ↔ far away in a big room (reverb).	CC 70 **Space** close ↔ far away in a big room (reverb).	CC 71 **Space** a little room and echo ↔ far away (reverb + dub echo).	CC 72 **Space** a little room ↔ far away (reverb).	CC 73 **Space** some room and echo ↔ far away in space.	CC 74 **Space** dry ↔ far away (reverb).	CC 75 **Space** nearly dry ↔ far away (reverb).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Swell** 0 = held chords. Up = the chord is re-struck on every half bar and breathes in and out.	CC 78 **Pump** 0 = long held chords ↔ the kick pumps the pad on every beat, deeper and deeper.	CC 79 **Complexity** few notes ↔ the loop fills in and new notes join one by one, reaching further up and down.	CC 80 **Variation** the figure as written ↔ stabs repeat in quick 16ths and jump an octave, at random.	CC 81 **Voices** 0 = one voice, 0.4 = + a third, 0.75 = + a fifth ↔ top: + the 7th, the voices strum apart and the phrase spills into the other bars.	CC 82 **Density** claves + shaker ↔ + metal ticks ↔ + electronic zaps ↔ top quarter: quick 32nd doubles.	CC 83 **Amount** 0 = only the breathing noise. Up = the chord pulses along in loose 8ths, at 1 also a 16th shimmer an octave up.	CC 36 **Tension** build-up: echo grows (answer, sequence), filters open, only in the last fifth a snare roll (clap fader). 0 = release.
Fader Level	CC 53 **Level** dark pad.	CC 54 **Level** dark techno pad on the progression.	CC 55 **Level** hypnotic loop on the chord.	CC 56 **Level** hypnotic stab on the chord root.	CC 57 **Level** counter blips, a short phrase every second bar.	CC 58 **Level** dark fast percussion.	CC 59 **Level** slow, uneven breathing.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 85 **Change** next of 8 chord progressions, for all.	CC 86 **Change** minor 7 → fourths → fifths → minor 9 without the 3rd.	CC 87 **Change** next of 8 loops (3, 5 or 7 steps).	CC 88 **Change** next of 8 stab figures.	CC 89 **Change** next of 8 phrase rhythms (new notes too).	CC 90 **Change** next of 8 clave figures.	CC 91 **Change** one breath per 2 → 4 → 8 → 1 bar(s).	CC 44 **Drop fill** hold while the beat is out: 4-bar fill from the next bar, the beat is back after the 16th beat. Let go = stop.
Button 2 Moment	CC 93 **Freeze** holds the current chord while held, for everybody.	CC 94 **Echo throw** long echo on the pad while held.	CC 95 **Octave** one octave up while held.	CC 96 **Echo throw** long echo on the stab while held.	CC 97 **Answer** random extra answers while held.	CC 98 **Roll** shaker and metal roll in 32nds, fuller and louder the longer it is held.	CC 99 **Open** the breath opens fully while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Playing together

Jojo builds the floor: kick first, rumble right next to it, then sub and hats, then clap, bassline and the groove (percussion, ride).

Jonas colours it: pad first, then the techno pad under it (all knobs at 0 is a good start), then dark percussion and the sequence. Stab and answer are for the peaks, the breathing FX for long transitions.

The pad's button 1 changes the chords for both players: Jojo's sub and bassline move with it. Pad button 2 (freeze) holds the chord for everybody.

Break: one press takes out kick, rumble, sub, bassline and clap at the next bar; hats, percussion, ride and all of Jonas' sounds keep going. Turn Tension up during the break, press again: everything is back on the one. Then let Tension go.

Drop fill: while the beat is out, hold global button 1. From the next bar a 4-bar fill builds (kick and snare get denser bar by bar, a noise sweep rises); after the 16th beat the beat is back. Let go earlier = the fill stops, the beat stays out.

Both Launch Controls have the full layout and steer the same sounds: whoever moves a control last sets its value, a button press counts from either. Agree who plays which page.

Every position sounds good

No filter closes completely. Sequence, answer and FX keep a little room even at space 0.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.