Launch Control XL 3 — Track 010 — ambient house

Ambient house in D minor, 120 BPM, a sunrise mood. Jojo plays the foundation (kick, bass, drums, congas), Jonas the colour (pad, chords, melodies, birds) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Chapter (Jonas, column 8) changes the chords for everybody at the next 4-bar phrase.

Every Launch Control XL 3 gets this full layout: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Shaker / Ride) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages. Two controllers: the control moved last wins.

Knob | Fader | Button | global (all modes) | unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Kick	2 Atmo Pump	3 Sub	4 Bassline	5 Clap / Rim	6 Hats	7 Congas	8 Global
Row 1 Brightness	CC 13 **Brightness** 0 = firm, round kick with a little click ↔ clicky attack (lpf 1.5–10 kHz).	CC 14 **Brightness** dull whoosh ↔ airy hiss (lpf 1.5–12 kHz).	CC 15 **Brightness** 0 = sine with a few overtones (audible on small speakers) ↔ warm and full.	CC 16 **Brightness** 0 = round and woody ↔ warm buzz (lpf 250–2000 Hz + envelope).	CC 17 **Brightness** 0 = natural, a little soft ↔ sharp crack (lpf 3.5–14 kHz).	CC 18 **Brightness** soft hiss ↔ crisp and sharp (lpf 3–16 kHz).	CC 19 **Brightness** soft and woody ↔ crisp slap (lpf 600–12000 Hz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if heard from outside the tent.
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** dry ↔ far away (reverb + echo).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ a little room (reverb).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Softness** 0 = firm 909 kick ↔ 1 = deep, soft thump without click.	CC 30 **Motion** still ↔ the filter breathes and the noise wanders left and right.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Groove** the line as it is ↔ extra 16th notes rolling in between.	CC 33 **Ghost notes** plain ↔ a quiet rim before beat 3 ↔ + small double taps.	CC 34 **Density** the pattern as it is ↔ + quiet 16ths ↔ + little 32nd rolls.	CC 35 **Density** steady pattern ↔ + fingertip ghost notes ↔ + agogo bells.	CC 36 **Tension** build-up: echo grows, filters open (not hats, clap, shaker), from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 5 **Level** 0 = gone. Four-on-the-floor kick, tuned to D.	CC 6 **Level** noise that pumps with the kick.	CC 7 **Level** sub on the chord root, follows the chapter.	CC 8 **Level** rolling bass, follows the chapter.	CC 9 **Level** clap / rim on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** off-beat hat. Keeps playing in the break.	CC 11 **Level** congas and bongos. Keep playing in the break.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** straight → pickup before the 1 → gap every 4th bar.	CC 38 **Change** pump → off-beat breath → slow waves.	CC 39 **Change** pump → off-beat → one long note per bar.	CC 40 **Change** rolling → off-beat → melodic.	CC 41 **Change** clap → rim with a pickup → clap + rim.	CC 42 **Change** off-beat → + 16ths → shuffled 16ths.	CC 43 **Change** pillow → rolling → latin.	CC 44 **Chapter** next chord progression for all, at the next 4-bar phrase.
Button 2 Moment	CC 45 **Drop out** kick pauses while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 **Slide** every note bends up into its pitch while held.	CC 48 **Octave** one octave up while held.	CC 49 **Roll** snare roll, growing over the bar, while held.	CC 50 **Open** long open hats on every 8th while held.	CC 51 **Fill** a conga run over the bar while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Pad	2 Deep Chords	3 Pluck Arp	4 Lead	5 Marimba	6 Glockenspiel	7 Birds	8 Global
Row 1 Brightness	CC 61 **Brightness** muffled ↔ open and airy (lpf 300–5000 Hz).	CC 62 **Brightness** warm and muffled ↔ bright, barking (lpf 600–8000 Hz).	CC 63 **Brightness** soft, woody plucks ↔ clear, sparkling (lpf 900–8000 Hz).	CC 64 **Brightness** soft and hushed ↔ open, clear voice (lpf 600–5000 Hz).	CC 65 **Brightness** soft, woody ↔ clear and bright (lpf 1.2–9 kHz).	CC 66 **Brightness** soft glow ↔ ringing, bright (lpf 3–16 kHz).	CC 67 **Brightness** far, muffled birds ↔ close and clear (lpf 2–14 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if heard from outside the tent.
Row 2 Space	CC 69 **Space** dry and close ↔ far away in a big room (reverb + echo).	CC 70 **Space** dry ↔ the dotted-8th echoes repeat far into the room.	CC 71 **Space** a little room ↔ far away (reverb + echo).	CC 72 **Space** a little room ↔ far away (reverb + echo).	CC 73 **Space** some room and echo ↔ far away.	CC 74 **Space** dry ↔ far away (reverb + echo).	CC 75 **Space** a little room ↔ far away across the field (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Swell** still ↔ slowly breathing in and out (every 2 bars).	CC 78 **Rhythm** long ringing chords ↔ short, choppy stabs.	CC 79 **Range** some notes left out ↔ every 16th, plus passing notes (9th, 6th).	CC 80 **Glide** plain notes ↔ notes bend gently into their pitch (at most a semitone).	CC 81 **Voices** 0 = one voice, 0.5 = + a third above, 1 = + a fifth: three-part marimba.	CC 82 **Density** a few notes per bar ↔ a busy pattern (~60 % of the 16ths).	CC 83 **Amount** a few calls ↔ a busy dawn chorus, an octave higher too.	CC 36 **Tension** build-up: echo grows, filters open (not hats, clap, shaker), from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 53 **Level** warm pad on the chapter's chords.	CC 54 **Level** chord stabs on the chapter's chords.	CC 55 **Level** pluck arp on the chord.	CC 56 **Level** slow lead on the chord.	CC 57 **Level** marimba phrase, every second bar.	CC 58 **Level** glockenspiel on the chord.	CC 59 **Level** bird chirps on the chord.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 85 **Change** voicing: warm → open (9th) → wide.	CC 86 **Change** next of 8 deep-house rhythms.	CC 87 **Change** next of 8 arp shapes.	CC 88 **Change** next of 8 melodies.	CC 89 **Change** next of 8 phrase rhythms (new notes too).	CC 90 **Change** next of 8 random patterns.	CC 91 **Change** next of 8 call rhythms (new notes too).	CC 44 **Chapter** next chord progression for all, at the next 4-bar phrase.
Button 2 Moment	CC 93 **Freeze** holds the current chord while held, for everybody.	CC 94 **Stab** a chord on every off-beat while held.	CC 95 **Octave** one octave up while held.	CC 96 **Echo throw** long echo on the lead while held.	CC 97 **Answer** the phrase plays in every bar while held.	CC 98 **Run** runs up and down the chord, denser and louder the longer it is held (full after 2 bars).	CC 99 **Flock** a whole flock calls while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Sunrise

Start like the sky before dawn: Jonas brings pad and birds, Jojo the atmo pump and the sub. The kick comes only when both are ready.

Playing together

Jojo builds the floor: kick, sub, off-beat hats, then the rolling bass and the groove (congas, shaker). Keep it dry; the room belongs to Jonas.

Jonas colours it: pad and deep chords first (all knobs at 0 is a good start), then arp and marimba. The lead is for the long, slow moments.

Chapter changes the chords for both players at the next 4-bar phrase: sub, bass and every melody follow. Pad button 2 (freeze) holds the chord for everybody.

Both Launch Controls have the full layout and steer the same sounds: whoever moves a control last sets its value, a button press counts from either. Agree who plays which page.

Build-up and drop

Jonas turns Tension up (echo, open filters, snare roll), presses Break at the top: the beat goes out, pad and birds float. Jojo holds the atmo riser, Jonas presses Break again: back on the one. Then let Tension go.

Every position sounds good

No filter closes completely. Arp, lead and marimba keep a little room even at space 0.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.