Launch Control XL 3 — Track 010 — ambient house (two controllers)

Ambient house in D minor, 120 BPM, a sunrise mood. Jojo plays the foundation (kick, bass, drums, congas), Jonas the colour (pad, chords, melodies, birds) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Chapter (Jonas, column 8) changes the chords for everybody at the next 4-bar phrase.

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Knob | Fader | Button | global (all modes) | unused

Jojo — Foundation (beat + bass)

	1 Kick	2 Atmo Pump	3 Sub	4 Bassline	5 Clap / Rim	6 Hats	7 Congas	8 Shaker / Ride
Row 1 Brightness	CC 13 **Brightness** 0 = firm, round kick with a little click ↔ clicky attack (lpf 1.5–10 kHz).	CC 14 **Brightness** dull whoosh ↔ airy hiss (lpf 1.5–12 kHz).	CC 15 **Brightness** 0 = sine with a few overtones (audible on small speakers) ↔ warm and full.	CC 16 **Brightness** 0 = round and woody ↔ warm buzz (lpf 250–2000 Hz + envelope).	CC 17 **Brightness** soft and far ↔ sharp crack (lpf 1.5–12 kHz).	CC 18 **Brightness** soft hiss ↔ crisp and sharp (lpf 3–16 kHz).	CC 19 **Brightness** soft and woody ↔ crisp slap (lpf 600–12000 Hz).	CC 20 **Brightness** soft shimmer ↔ bright sizzle (lpf 4.5–16 kHz).
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** dry ↔ far away (reverb + echo).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ a little room (reverb).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Space** dry ↔ far away (reverb + echo).
Row 3 Character	CC 29 **Softness** 0 = firm 909 kick ↔ 1 = deep, soft thump without click.	CC 30 **Motion** still ↔ the filter breathes and the noise wanders left and right.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Groove** the line as it is ↔ extra 16th notes rolling in between.	CC 33 **Ghost notes** plain ↔ a quiet rim before beat 3 ↔ + small double taps.	CC 34 **Density** the pattern as it is ↔ + quiet 16ths ↔ + little 32nd rolls.	CC 35 **Density** steady pattern ↔ + fingertip ghost notes ↔ + agogo bells.	CC 36 **Swing** straight ↔ swung, lazy (the in-between 16ths come late).
Fader Level	CC 5 **Level** 0 = gone. Four-on-the-floor kick, tuned to D.	CC 6 **Level** noise that pumps with the kick.	CC 7 **Level** sub on the chord root, follows the chapter.	CC 8 **Level** rolling bass, follows the chapter.	CC 9 **Level** clap / rim on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** off-beat hat. Keeps playing in the break.	CC 11 **Level** congas and bongos. Keep playing in the break.	CC 12 **Level** shaker and ride. Keep playing in the break.
Button 1 Change	CC 37 **Change** straight → pickup before the 1 → gap every 4th bar.	CC 38 **Change** pump → off-beat breath → slow waves.	CC 39 **Change** pump → off-beat → one long note per bar.	CC 40 **Change** rolling → off-beat → melodic.	CC 41 **Change** clap → rim with a pickup → clap + rim.	CC 42 **Change** off-beat → + 16ths → shuffled 16ths.	CC 43 **Change** pillow → rolling → latin.	CC 44 **Change** shaker → ride → both.
Button 2 Moment	CC 45 **Drop out** kick pauses while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 **Slide** every note bends up into its pitch while held.	CC 48 **Octave** one octave up while held.	CC 49 **Roll** snare roll, growing over the bar, while held.	CC 50 **Open** long open hats on every 8th while held.	CC 51 **Fill** a conga run over the bar while held.	CC 52 **Double** double time while held.

Jonas — Colour (chords + melodies) · column 8 = global

	1 Pad	2 Deep Chords	3 Pluck Arp	4 Lead	5 Marimba	6 Glass Bells	7 Birds	8 Global
Row 1 Brightness	CC 13 **Brightness** muffled ↔ open and airy (lpf 300–5000 Hz).	CC 14 **Brightness** warm and muffled ↔ bright, barking (lpf 600–8000 Hz).	CC 15 **Brightness** soft, woody plucks ↔ clear, sparkling (lpf 900–8000 Hz).	CC 16 **Brightness** soft and hushed ↔ open, clear voice (lpf 600–5000 Hz).	CC 17 **Brightness** soft, woody ↔ clear and bright (lpf 1.2–9 kHz).	CC 18 **Brightness** soft glow ↔ glittering (lpf 3–16 kHz).	CC 19 **Brightness** far, muffled birds ↔ close and clear (lpf 2–14 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if heard from outside the tent.
Row 2 Space	CC 21 **Space** dry and close ↔ far away in a big room (reverb + echo).	CC 22 **Space** dry ↔ the dotted-8th echoes repeat far into the room.	CC 23 **Space** a little room ↔ far away (reverb + echo).	CC 24 **Space** a little room ↔ far away (reverb + echo).	CC 25 **Space** some room and echo ↔ far away.	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** a little room ↔ far away across the field (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Swell** still ↔ slowly breathing in and out (every 2 bars).	CC 30 **Rhythm** long ringing chords ↔ short, choppy stabs.	CC 31 **Range** some notes left out ↔ every 16th, plus passing notes (9th, 6th).	CC 32 **Glide** plain notes ↔ notes bend gently into their pitch (at most a semitone).	CC 33 **Voices** 0 = one voice, 0.5 = + a third above, 1 = + a fifth: three-part marimba.	CC 34 **Density** a few bells per bar ↔ a rain of bells (~60 % of the 16ths).	CC 35 **Amount** a few calls ↔ a busy dawn chorus, an octave higher too.	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 5 **Level** warm pad on the chapter's chords.	CC 6 **Level** chord stabs on the chapter's chords.	CC 7 **Level** pluck arp on the chord.	CC 8 **Level** slow lead on the chord.	CC 9 **Level** marimba phrase, every second bar.	CC 10 **Level** glass bells on the chord.	CC 11 **Level** bird chirps on the chord.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** voicing: warm → open (9th) → wide.	CC 38 **Change** next of 8 deep-house rhythms.	CC 39 **Change** next of 8 arp shapes.	CC 40 **Change** next of 8 melodies.	CC 41 **Change** next of 8 phrase rhythms (new notes too).	CC 42 **Change** next of 8 random bell patterns.	CC 43 **Change** next of 8 call rhythms (new notes too).	CC 44 **Chapter** next chord progression for all, at the next 4-bar phrase.
Button 2 Moment	CC 45 **Freeze** holds the current chord while held, for everybody.	CC 46 **Stab** a chord on every off-beat while held.	CC 47 **Octave** one octave up while held.	CC 48 **Echo throw** long echo on the lead while held.	CC 49 **Answer** the phrase plays in every bar while held.	CC 50 **Burst** a quick rain of bells while held.	CC 51 **Flock** a whole flock calls while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Sunrise

Start like the sky before dawn: Jonas brings pad and birds, Jojo the atmo pump and the sub. The kick comes only when both are ready.

Playing together

Jojo builds the floor: kick, sub, off-beat hats, then the rolling bass and the groove (congas, shaker). Keep it dry; the room belongs to Jonas.

Jonas colours it: pad and deep chords first (all knobs at 0 is a good start), then arp and marimba. The lead is for the long, slow moments.

Chapter changes the chords for both players at the next 4-bar phrase: sub, bass and every melody follow. Pad button 2 (freeze) holds the chord for everybody.

Build-up and drop

Jonas turns Tension up (echo, open filters, snare roll), presses Break at the top: the beat goes out, pad and birds float. Jojo holds the atmo riser, Jonas presses Break again: back on the one. Then let Tension go.

Every position sounds good

No filter closes completely. Arp, lead and marimba keep a little room even at space 0.