Launch Control XL 3 — House Bass 3 (lab/bass, 009 Jojo 4: columns = 8 sounds, button 1 = the same 24 lines everywhere)

Columns = sounds: 1 FM (Daft Punk), 2 Juno, 3 M1 organ, 4 disco pluck, 5 round, 6 warm analog, 7 Jojo 4 now, 8 deep sub.

Button 1 = the same 24 lines in every column, by family: Voyager, Instant Crush, Get Lucky, disco syncope, octave funk, Something About Us, beat 4 open, dead-note funk.

Knob | Fader | Button | unused

Mode 16 — Sounds

	1 FM (Daft Punk)	2 Juno	3 M1 organ	4 Disco pluck	5 Round	6 Warm analog	7 Jojo 4 now	8 Deep sub
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (low-pass over the sound's range).	CC 14 **Brightness** as 1 FM (Daft Punk)	CC 15 **Brightness** as 1 FM (Daft Punk)	CC 16 **Brightness** as 1 FM (Daft Punk)	CC 17 **Brightness** as 1 FM (Daft Punk)	CC 18 **Brightness** as 1 FM (Daft Punk)	CC 19 **Brightness** as 1 FM (Daft Punk)	CC 20 **Brightness** as 1 FM (Daft Punk)
Row 2 Space	CC 21 **Space** dry ↔ echo and room (keep it low for a bass).	CC 22 **Space** as 1 FM (Daft Punk)	CC 23 **Space** as 1 FM (Daft Punk)	CC 24 **Space** as 1 FM (Daft Punk)	CC 25 **Space** as 1 FM (Daft Punk)	CC 26 **Space** as 1 FM (Daft Punk)	CC 27 **Space** as 1 FM (Daft Punk)	CC 28 **Space** as 1 FM (Daft Punk)
Row 3 Length	CC 29 **Length** the lines' own note lengths × 0.5 … × 4.	CC 30 **Length** as 1 FM (Daft Punk)	CC 31 **Length** as 1 FM (Daft Punk)	CC 32 **Length** as 1 FM (Daft Punk)	CC 33 **Length** as 1 FM (Daft Punk)	CC 34 **Length** as 1 FM (Daft Punk)	CC 35 **Length** as 1 FM (Daft Punk)	CC 36 **Length** as 1 FM (Daft Punk)
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 FM (Daft Punk)	CC 7 **Level** as 1 FM (Daft Punk)	CC 8 **Level** as 1 FM (Daft Punk)	CC 9 **Level** as 1 FM (Daft Punk)	CC 10 **Level** as 1 FM (Daft Punk)	CC 11 **Level** as 1 FM (Daft Punk)	CC 12 **Level** as 1 FM (Daft Punk)
Button 1 Line	CC 37 **Line** next of the same 24 lines (at the next bar).	CC 38 **Line** as 1 FM (Daft Punk)	CC 39 **Line** as 1 FM (Daft Punk)	CC 40 **Line** as 1 FM (Daft Punk)	CC 41 **Line** as 1 FM (Daft Punk)	CC 42 **Line** as 1 FM (Daft Punk)	CC 43 **Line** as 1 FM (Daft Punk)	CC 44 **Line** as 1 FM (Daft Punk)
Button 2 Octave	CC 45 **Octave** one octave up while held.	CC 46 **Octave** as 1 FM (Daft Punk)	CC 47 **Octave** as 1 FM (Daft Punk)	CC 48 **Octave** as 1 FM (Daft Punk)	CC 49 **Octave** as 1 FM (Daft Punk)	CC 50 **Octave** as 1 FM (Daft Punk)	CC 51 **Octave** as 1 FM (Daft Punk)	CC 52 **Octave** as 1 FM (Daft Punk)

Mode 2 — Context

	1	2	3	4	5 Progression	6 Drums	7 Simple bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Simple bass** off-beat triangle on the root (starts at 0 here).	CC 60 **Keys** the keys of 009 (Steinway + Rhodes, chain rhythm), following the progression.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Next** next progression (all 21), at the next 8-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 **Previous** previous progression, at the next 8-bar phrase.	CC 98 **Drums out** bass and keys alone while held.	CC 99 —	CC 100 —

Guide

What to listen for

Pick a line, then sweep the sounds; pick a sound, then step through the lines.

Progressions

Mode 2 col. 5: the lines walk into every change.