Launch Control XL 3 — Ambient Harmonie 3 (lab/harmonie, 007: Takada marimba + a melodic voice)

Columns 1–4 = Takada-style marimba variants, 5 vibraphone motif, 6 flute, 7 Eno bowed (on at the start). All in D lydian over 007's context (Mode 2).

Knob Fader Button unused

Mode 16 — Candidates

	1 Takada 3:4	2 Takada 5·7·12	3 Canon	4 Additive	5 Vibes Motif	6 Flute	7 Eno Bowed	8
Row 1 Brightness	CC 13 **Brightness** soft mallet ↔ bright (low-pass over the sound's range).	CC 14 **Brightness** as 1 Takada 3:4	CC 15 **Brightness** as 1 Takada 3:4	CC 16 **Brightness** as 1 Takada 3:4	CC 17 **Brightness** as 1 Takada 3:4	CC 18 **Brightness** as 1 Takada 3:4	CC 19 **Brightness** as 1 Takada 3:4	CC 20 —
Row 2 Space	CC 21 **Space** room and dotted-8th echo (a little at 0).	CC 22 **Space** as 1 Takada 3:4	CC 23 **Space** as 1 Takada 3:4	CC 24 **Space** as 1 Takada 3:4	CC 25 **Space** as 1 Takada 3:4	CC 26 **Space** as 1 Takada 3:4	CC 27 **Space** as 1 Takada 3:4	CC 28 —
Row 3 Character	CC 29 **Layers** 0 = one figure ↔ all figures (3 / 4) on top of each other.	CC 30 **Layers** as 1 Takada 3:4	CC 31 **Voices** 0 = one voice ↔ 4 voices entering later.	CC 32 **Layers** 0 = the growing figure alone ↔ + steady layers.	CC 33 **Length** shorter ↔ longer notes.	CC 34 **Length** as 5 Vibes Motif	CC 35 **Voices** 2 loops ↔ 6 loops drifting against each other.	CC 36 —
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Takada 3:4	CC 7 **Level** as 1 Takada 3:4	CC 8 **Level** as 1 Takada 3:4	CC 9 **Level** as 1 Takada 3:4	CC 10 **Level** as 1 Takada 3:4	CC 11 **Level** as 1 Takada 3:4	CC 12 —
Button 1 Change	CC 37 **Change** figure set: open → bright → low.	CC 38 **Change** as 1 Takada 3:4	CC 39 **Change** 3 figures.	CC 40 **Change** 3 figures.	CC 41 **Change** motif → half speed → octave up.	CC 42 **Change** ocarina → pan flute → shakuhachi.	CC 43 **Change** note set: open → middle → high.	CC 44 —
Button 2 Moment	CC 45 **Echo throw** held: long dotted-8th echo.	CC 46 **Echo throw** as 1 Takada 3:4	CC 47 **Echo throw** as 1 Takada 3:4	CC 48 **Echo throw** as 1 Takada 3:4	CC 49 **Echo throw** as 1 Takada 3:4	CC 50 **Echo throw** as 1 Takada 3:4	CC 51 **Echo throw** as 1 Takada 3:4	CC 52 —

Mode 2 — Context

	1	2	3	4	5 Progression	6 Heartbeat	7 Drone	8 Pad
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 —	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Heartbeat** 007's soft pulse on D.	CC 59 **Drone** D–A drone, swelling every 2 bars.	CC 60 **Pad** 007's pad, high-passed (less mud).
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Progression** next of 3, at the next 8 bars.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 **Back** previous progression.	CC 98 **Pulse out** the pulse pauses while held.	CC 99 —	CC 100 —

Guide

What to listen for

Which marimba layering moves without getting busy? Row 3 adds the layers one by one. Which voice on top guides the ear: vibraphone or flute?