Launch Control XL 3 — Mallets Lab 2 (lab/mallets, round 2 for 009 column 5: real mallets, polymeter loops)

Real vibraphone, balafon, kalimba (VCSL) and marimba (VSCO 2), all CC0; played as 008's sequence: 5- and 7-step loops, small changes per bar.

Mode 2: fader 6 = drums (knob 1 = swing, button 2 = drums out), fader 7 = bass, fader 8 = keys of 009; column 5 button 1 = harmony (one chord ↔ Am9/D9).

Knob | Fader | Button | unused

Mode 16 — Candidates

	1 Vibraphone	2 Balafon	3 Kalimba	4 Marimba	5	6	7	8
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright over the sound's own range; brighter also plays a little harder (±2 dB).	CC 14 **Brightness** as 1 Vibraphone	CC 15 **Brightness** as 1 Vibraphone	CC 16 **Brightness** as 1 Vibraphone	CC 17 —	CC 18 —	CC 19 —	CC 20 —
Row 2 Space	CC 21 **Space** 0 = dry; a 1/8 echo from the first turn (full at half), the room joins from a third on.	CC 22 **Space** as 1 Vibraphone	CC 23 **Space** as 1 Vibraphone	CC 24 **Space** as 1 Vibraphone	CC 25 —	CC 26 —	CC 27 —	CC 28 —
Row 3 Length	CC 29 **Length** 0 = damped ↔ rings four times longer.	CC 30 **Length** as 1 Vibraphone	CC 31 **Length** as 1 Vibraphone	CC 32 **Length** as 1 Vibraphone	CC 33 —	CC 34 —	CC 35 —	CC 36 —
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Vibraphone	CC 7 **Level** as 1 Vibraphone	CC 8 **Level** as 1 Vibraphone	CC 9 —	CC 10 —	CC 11 —	CC 12 —
Button 1 Change	CC 37 **Change** 5-step loop → 7-step loop → call + echo → riff, next bar.	CC 38 **Change** as 1 Vibraphone	CC 39 **Change** as 1 Vibraphone	CC 40 **Change** as 1 Vibraphone	CC 41 —	CC 42 —	CC 43 —	CC 44 —
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo, the tail rings on.	CC 46 **Echo throw** as 1 Vibraphone	CC 47 **Echo throw** as 1 Vibraphone	CC 48 **Echo throw** as 1 Vibraphone	CC 49 —	CC 50 —	CC 51 —	CC 52 —

Mode 2 — Context

	1	2	3	4	5 Harmony	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009 (Steinway + Rhodes, chain rhythm), to hear the answers.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Harmony** Ein Akkord ↔ Wechsel, at the next 4-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 **Drums out** horns, keys and bass alone while held.	CC 99 —	CC 100 —

Guide

What to listen for

Does it groove now (loops against the bar)? Which wood / metal fits the keys?

Harmony

Ein Akkord: Am9. Wechsel: Am9 2 bars, D9 2 bars. The mallets stay in A dorian over both.