Launch Control XL 3 — House Keys Lab (lab/keys/old, round 1 for 009)

Eight candidates for the one chord instrument of 009, one per column, each built like a track column: brightness, space, character, level, change (3 patterns, at the next bar), moment (while held).

Pull up one candidate at a time. Drums and bass run by themselves; Mode 2, column 1 changes them (and the progression).

The status box at the bottom right shows each candidate's pattern (→ next one after a press); "⍰ LC groß" opens the live view in a big window.

Knob | Fader | Button | unused

Mode 16 — Candidates

	1 M1 Pump	2 Grand 3-3-2	3 Rhodes Call	4 Gospel Organ	5 Organ Stab Funk	6 Synth Stab	7 Piano Bounce	8 Clavinet Disco
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (lpf 1.5–14 kHz).	CC 14 **Brightness** warm ↔ open (lpf 1.5–14 kHz).	CC 15 **Brightness** mellow ↔ barking (lpf 1–9 kHz).	CC 16 **Brightness** round ↔ cutting (lpf 1–10 kHz).	CC 17 **Brightness** dark ↔ clicky (lpf 1–10 kHz).	CC 18 **Brightness** muted ↔ open (lpf 0.4–4 kHz + envelope).	CC 19 **Brightness** soft ↔ bright (lpf 1.5–14 kHz).	CC 20 **Brightness** soft ↔ snappy (lpf 1.5–12 kHz).
Row 2 Space	CC 21 **Space** 0 = dry ↔ a room.	CC 22 **Space** 0 = dry ↔ a room.	CC 23 **Space** 0 = dry ↔ a room.	CC 24 **Space** 0 = dry ↔ a room.	CC 25 **Space** 0 = dry ↔ a room.	CC 26 **Space** 0 = dry ↔ a room.	CC 27 **Space** 0 = dry ↔ a room.	CC 28 **Space** 0 = dry ↔ a room.
Row 3 Character	CC 29 **Sound** 0 = M1-style piano ↔ organ layered in.	CC 30 **Length** 0 = short stabs ↔ hits ring three times longer.	CC 31 **Randomness** 0 = written ↔ every bar a little different.	CC 32 **Sound** 0 = drawbar organ ↔ percussive organ.	CC 33 **Randomness** 0 = written ↔ every bar a little different.	CC 34 **Bite** 0 = soft stab ↔ resonant, snapping filter.	CC 35 **Randomness** 0 = written ↔ every bar a little different.	CC 36 **Wah** 0 = plain ↔ an auto-wah on every hit.
Fader Level	CC 5 **Level** M1-style piano on the off-beats.	CC 6 **Level** dry grand piano, 3-3-2 stabs.	CC 7 **Level** Rhodes: a long chord, answered by single top notes.	CC 8 **Level** gospel organ, left hand and chords alternate.	CC 9 **Level** short organ stabs on syncopated 16ths.	CC 10 **Level** saw chord stab, sparse.	CC 11 **Level** piano + a little synth stab: lower and upper half bounce.	CC 12 **Level** clavinet: funky, plucked disco chords.
Button 1 Change	CC 37 **Change** pump → push → half.	CC 38 **Change** 3-3-2 → held → with an answer.	CC 39 **Change** call → long + answer → stabs + answer.	CC 40 **Change** roll → shuffle → stops.	CC 41 **Change** funk → off-beat stabs → two-bar figure.	CC 42 **Change** one hit → long + fill → syncopated.	CC 43 **Change** bounce → half bounce → 16th bounce.	CC 44 **Change** disco → answer → stutter.
Button 2 Moment	CC 45 **Octave** top note doubled an octave up while held.	CC 46 **Pedal** sustain pedal while held: chords ring on.	CC 47 **Phaser** slow phaser swirl while held.	CC 48 **Leslie** fast vibrato while held.	CC 49 **Roll** chords on every 16th while held.	CC 50 **Echo throw** long echo while held.	CC 51 **Octave** everything an octave up while held.	CC 52 **Stutter** chords on every 16th while held.

Mode 2 — Global (column 1)

	1 Global	2	3	4	5	6	7	8
Row 1	CC 61 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 —	CC 67 —	CC 68 —
Row 2	CC 69 **Humanize** 0 = machine ↔ loose velocity and timing.	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 **Bass** 0 = no bass ↔ off-beat bass on the chord root.	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 —	CC 59 —	CC 60 —
Buttons 1	CC 85 **Progression** sunny → deep → gospel, at the next 4 bars.	CC 86 —	CC 87 —	CC 88 —	CC 89 —	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 **Drums out** keys (and bass) alone while held.	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 —	CC 99 —	CC 100 —

Guide

How to judge

Keys in house play against the kick and the bass, not alone: judge with the drums on. Give each candidate at least 8 bars and all three patterns. Hold Drums out (Mode 2, column 1, button 2) to hear the keys alone.

Randomness

Columns 3, 5 and 7 have randomness on knob 3: 0 = the written two-bar pattern, up = each bar a little different (hits drop out, ghost chords, a fill at the end of the phrase).

Feel

Swing (Mode 2, column 1, knob 1) at 55-58 % is the classic house shuffle.