Launch Control XL 3 — Track 007 — ambient moods (two controllers)

Dreamy ambient on D, about 70 BPM. Jojo plays the foundation (heartbeat, drone, bass and soft clicks), Jonas the colour (pad, chords, melodies) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar, 3 per stem), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up.

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Knob | Fader | Button | global (all modes) | unused

Jojo — Foundation (beat + bass)

	1 Pulse	2 Sea / Wind	3 Drone	4 Bass	5 Rim	6 Ticks	7 Wood / Drops	8 Crackle
Row 1 Brightness	CC 13 **Brightness** dull thump ↔ clicky attack (lpf 180–1500 Hz).	CC 14 **Brightness** 0 = soft rumble ↔ airy hiss (lpf 700–12000 Hz, moves with the waves).	CC 15 **Brightness** pure and dark ↔ open, the overtones come through (lpf 120–4000 Hz).	CC 16 **Brightness** round and dark ↔ the saw's buzz comes through (lpf 80–2000 Hz).	CC 17 **Brightness** soft and far ↔ sharp crack (lpf 1.2–12 kHz).	CC 18 **Brightness** soft tick ↔ crisp and sharp (lpf 3–16 kHz).	CC 19 **Brightness** woody (pure sine blip) ↔ metallic (FM).	CC 20 **Brightness** 0 = soft crackle ↔ bright sizzle (lpf 5–16 kHz).
Row 2 Space	CC 21 **Space** dry and close ↔ far away in a big room (reverb).	CC 22 **Space** dry ↔ far away (reverb).	CC 23 **Space** dry ↔ far away (reverb).	CC 24 **Space** dry ↔ far away (reverb).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Space** dry ↔ far away (reverb + echo).
Row 3 Character	CC 29 **Drive** three steps: soft sine thump → synth kick → firm kick with more click.	CC 30 **Sea ↔ Wind** 0 = brown-noise waves rolling in, 0.5 = both, 1 = only whistling wind gusts.	CC 31 **Beating** 0 = pure sines. Up = a detuned saw copy fades in, the two beat against each other (slow “wah-wah”).	CC 32 **Groove** 0 = a soft swell every bar. Up to 0.5 a 3-3-2 pulse fades in, at 1 only the pulse.	CC 33 **Ghost notes** plain ↔ extra quiet clicks in between.	CC 34 **Density** 8ths ↔ + 16ths ↔ + little flutters.	CC 35 **Density** a click now and then ↔ a busy pattern.	CC 36 **Density** a little dust ↔ heavy crackle.
Fader Level	CC 5 **Level** 0 = gone. A heartbeat thump on D.	CC 6 **Level** sea and wind. Keeps playing in the break.	CC 7 **Level** slow drone chords on D.	CC 8 **Level** slow bass swells.	CC 9 **Level** soft rim click on 2 and 4.	CC 10 **Level** clock ticks.	CC 11 **Level** wood clicks and drops.	CC 12 **Level** crackle, vinyl dust. Keeps playing in the break.
Button 1 Change	CC 37 **Change** heartbeat → quarters → half notes.	CC 38 **Change** next of 3 random wave / gust patterns.	CC 39 **Change** 3 drone chords per chapter: D–A → D–A–E → G–D–A.	CC 40 **Change** next of 3 bass lines (a note every 2 bars).	CC 41 **Change** backbeat → late ghost → offset click.	CC 42 **Change** next of 3 random accent / 16th patterns.	CC 43 **Change** next of 3 random patterns.	CC 44 **Change** next of 3 random crackle patterns.
Button 2 Moment	CC 45 **Drop out** pulse pauses while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 —	CC 48 **Octave** one octave up while held.	CC 49 **Roll** 16th roll, growing over the bar, while held.	CC 50 **Open** ticks ring long while held.	CC 51 **Fill** almost every 16th plays while held.	CC 52 **Double** twice as much crackle while held.

Jonas — Colour (chords + melodies) · column 8 = global

	1 Pad	2 Chords	3 Music Box	4 Whale	5 Choir	6 Glitter	7 Shimmer	8 Global
Row 1 Brightness	CC 13 **Brightness** muffled ↔ open and airy (lpf 300–8000 Hz).	CC 14 **Brightness** warm ↔ bright, glassy (lpf 400–10000 Hz).	CC 15 **Brightness** soft plucks ↔ sharp, sparkling (lpf 1.5–14 kHz).	CC 16 **Brightness** soft and round ↔ clear and nasal (lpf 300–6000 Hz).	CC 17 **Brightness** hushed ↔ clear (lpf 500–10000 Hz).	CC 18 **Brightness** soft mallets ↔ bright metal (lpf 3–16 kHz).	CC 19 **Brightness** dark whoosh ↔ bright shimmer (lpf 1.5–14 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: distant, under water.
Row 2 Space	CC 21 **Space** dry and close ↔ far away in a big room (reverb + echo).	CC 22 **Space** dry ↔ far away (reverb + echo).	CC 23 **Space** dry ↔ far away (reverb + echo).	CC 24 **Space** dry ↔ far away (reverb + echo).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Swell** 0 = still, held chords. Up = the chord is re-struck every half bar and breathes in and out.	CC 30 **Length** long ringing chords ↔ short, choppy stabs.	CC 31 **Density** a few notes of the tune ↔ every 8th plays.	CC 32 **Glide** how far each call slides into its note: 0 = ±2 semitones, 1 = ±12 (deep, eerie bends).	CC 33 **Voices** 0 = one voice, 0.5 = + a third above, 1 = + a fifth: three-part harmony.	CC 34 **Density** a drop now and then (~1 per bar) ↔ a sparkling rain (~70 % of the 16ths).	CC 35 **Amount** subtle (one tone) ↔ wild (a bell-like chord with long echoes).	CC 36 **Tension** 0–0.5: echo grows on all melodic stems, filters open. 0.5–1: + slow tape wobble on the long sounds. Back to 0 = release.
Fader Level	CC 5 **Level** long floating chords.	CC 6 **Level** soft chord pings over the pad (same chords as the pad).	CC 7 **Level** slow music box.	CC 8 **Level** whale calls, about two in three bars.	CC 9 **Level** choir voices.	CC 10 **Level** random glockenspiel notes.	CC 11 **Level** shimmer swells.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** 3 chord progressions: calm → circling → open.	CC 38 **Change** sparse (2 in 8) → medium (3 in 8) → busy (5 in 8).	CC 39 **Change** up and down → rising → lullaby.	CC 40 **Change** rare → normal → conversation (more calls).	CC 41 **Change** middle → low → high register (new melody each time).	CC 42 **Change** high → very high → middle register.	CC 43 **Change** a new tone every 2 bars → every 4 bars → every bar.	CC 44 **Chapter** lydian → dorian → whole tone, at the next bar.
Button 2 Moment	CC 45 **Freeze** holds the current chord while held.	CC 46 **Stab** chord stabs on every 8th while held.	CC 47 **Octave** one octave up while held.	CC 48 **Echo throw** long echo on the calls while held.	CC 49 **Full choir** all three voices while held.	CC 50 **Run** runs up and down the scale, denser and louder the longer it is held (full after 2 bars).	CC 51 **Rise** while held, a cloud of tones climbs an octave and grows denser over 2 bars.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Playing together

Jojo builds the floor: drone and bass first, then the heartbeat, then the small clicks. Jonas colours it: pad and chords, then whale, choir and the sparkles on top.

Jonas' column 8 acts on everything: Fog and Tension darken or open all filters, Room drowns everything in reverb, Chapter changes the key colour for both players at the next bar.

Break: one press takes out the beat (pulse, bass, rim, ticks, wood) at the next bar; drone, crackle, sea and all of Jonas' sounds keep floating. The second press brings the beat back on the one.

Every position sounds good

No filter closes completely, and space 0 is dry but never silent. Row 2 at about the middle gives each sound the room it had in the original track.