Launch Control XL 3 — Harmonie 1 (lab/harmonie, 009: harmony columns over switchable progressions)

Columns 1–3 strings type, 4–6 organ type. All follow the progression (Mode 2, column 5, button 1: next 8-bar phrase).

Progressions: Am9↔D9 2+2 · Am9↔D9 4+4 · MAW Am7 Cmaj7 Em7 · Attack 8 bars · Escravos? 3/8+5/8 · one chord.

Knob | Fader | Button | unused

Mode 16 — Candidates

	1 String machine	2 JX-10 strings	3 Real section	4 Organ as strings	5 B3 held	6 M1 stabs	7	8
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (low-pass over the sound's range).	CC 14 **Brightness** as 1 String machine	CC 15 **Brightness** as 1 String machine	CC 16 **Brightness** as 1 String machine	CC 17 **Brightness** as 1 String machine	CC 18 **Brightness** as 1 String machine	CC 19 —	CC 20 —
Row 2 Space	CC 21 **Space** echo and room.	CC 22 **Space** as 1 String machine	CC 23 **Space** as 1 String machine	CC 24 **Space** as 1 String machine	CC 25 **Space** as 1 String machine	CC 26 **Space** as 1 String machine	CC 27 —	CC 28 —
Row 3 Movement	CC 29 **Movement** PWM depth / detune.	CC 30 **Movement** as 1 String machine	CC 31 **Length** shorter ↔ full length.	CC 32 **Movement** vibrato / Leslie depth.	CC 33 **Movement** as 4 Organ as strings	CC 34 **Length** short ↔ long stabs.	CC 35 —	CC 36 —
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 String machine	CC 7 **Level** as 1 String machine	CC 8 **Level** as 1 String machine	CC 9 **Level** as 1 String machine	CC 10 **Level** as 1 String machine	CC 11 —	CC 12 —
Button 1 Rhythm	CC 37 **Rhythm** held → breathing → one off-beat stab per bar, next bar.	CC 38 **Rhythm** as 1 String machine	CC 39 **Rhythm** as 1 String machine	CC 40 **Rhythm** as 1 String machine	CC 41 **Rhythm** as 1 String machine	CC 42 **Rhythm** 1 per bar → off-beat 16ths → held, next bar.	CC 43 —	CC 44 —
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo.	CC 46 **Echo throw** as 1 String machine	CC 47 **Echo throw** as 1 String machine	CC 48 **Echo throw** as 1 String machine	CC 49 **Echo throw** as 1 String machine	CC 50 **Echo throw** as 1 String machine	CC 51 —	CC 52 —

Mode 2 — Context

	1	2	3	4	5 Progression	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009 (Steinway + Rhodes, chain rhythm), following the progression.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Progression** next progression, at the next 8-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 **Drums out** harmony, keys and bass alone while held.	CC 99 —	CC 100 —

Guide

What to listen for

Which progression carries a party for a long time? Which strings / organ type sits best under the keys?

Harmony

Mode 2 column 5 button 1 cycles the progression; the dashboard shows the chord now.