Launch Control XL 3 — Lead Lab 2 (lab/lead, round 2 for 009 column 3: real trumpet, flute, alto sax)

Real trumpet and flute (VSCO 2) and alto sax (Weresax), all CC0, against the pan flute of round 1. Same four ways of playing on every column.

Mode 2: fader 6 = drums (knob 1 = swing, button 2 = drums out), fader 7 = bass, fader 8 = keys of 009; column 5 button 1 = harmony (one chord ↔ Am9/D9).

Knob | Fader | Button | unused

Mode 16 — Candidates

	1 Trumpet	2 Flute	3 Alto sax	4 Pan flute	5	6	7	8
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright over the sound's own range; brighter also plays a little harder (±2 dB).	CC 14 **Brightness** as 1 Trumpet	CC 15 **Brightness** as 1 Trumpet	CC 16 **Brightness** as 1 Trumpet	CC 17 —	CC 18 —	CC 19 —	CC 20 —
Row 2 Space	CC 21 **Space** 0 = dry; a 1/8 echo from the first turn (full at half), the room joins from a third on.	CC 22 **Space** as 1 Trumpet	CC 23 **Space** as 1 Trumpet	CC 24 **Space** as 1 Trumpet	CC 25 —	CC 26 —	CC 27 —	CC 28 —
Row 3 Length	CC 29 **Length** 0 = detached notes ↔ legato, notes ring into each other.	CC 30 **Length** as 1 Trumpet	CC 31 **Length** as 1 Trumpet	CC 32 **Length** as 1 Trumpet	CC 33 —	CC 34 —	CC 35 —	CC 36 —
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Trumpet	CC 7 **Level** as 1 Trumpet	CC 8 **Level** as 1 Trumpet	CC 9 —	CC 10 —	CC 11 —	CC 12 —
Button 1 Change	CC 37 **Change** call + answer → impro → riff → long notes, next bar.	CC 38 **Change** as 1 Trumpet	CC 39 **Change** as 1 Trumpet	CC 40 **Change** as 1 Trumpet	CC 41 —	CC 42 —	CC 43 —	CC 44 —
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo, the tail rings on.	CC 46 **Echo throw** as 1 Trumpet	CC 47 **Echo throw** as 1 Trumpet	CC 48 **Echo throw** as 1 Trumpet	CC 49 —	CC 50 —	CC 51 —	CC 52 —

Mode 2 — Context

	1	2	3	4	5 Harmony	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009 (Steinway + Rhodes, chain rhythm), to hear the answers.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Harmony** Ein Akkord ↔ Wechsel, at the next 4-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 **Drums out** horns, keys and bass alone while held.	CC 99 —	CC 100 —

Generated from `lab/lead/lead-lab-2.strudel` — edit the `@ctl` comments in the track, not this sheet.

Guide

What to listen for

Which instrument carries a jazzy house lead? Does Impro feel improvised (and still good), or is the fixed riff better?

Harmony

Ein Akkord: Am9. Wechsel: Am9 2 bars, D9 2 bars. The lead stays in A dorian over both.