Launch Control XL 3 — House Keys Lab 20 (lab/keys, round 20 for 009: the free button in sound mode)

Four times the keys of 009 (Steinway + Rhodes Mark I); only button 1 in sound mode differs: 1 nothing (as now), 2 echo throw, 3 push on / off, 4 stutter.

Push is only audible with chord changes: Mode 2, column 5, button 1 switches the harmony to Wechsel (Am9 ↔ D9). Mode 2: fader 6 = drums (knob 1 = swing, button 2 = drums out), fader 7 = bass.

Knob | Fader | Button | unused

Mode 16 — Rhythms

	1 Status quo	2 Echo throw	3 Push	4 Stutter	5	6	7	8
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright over the sound's own range (lpf from 250 Hz); top third: a presence peak, brighter than raw; brighter also plays a little harder (±2 dB).	CC 14 **Brightness** as 1 Status quo	CC 15 **Brightness** as 1 Status quo	CC 16 **Brightness** as 1 Status quo	CC 17 —	CC 18 —	CC 19 —	CC 20 —
Row 2 Space	CC 21 **Space** 0 = dry; a 1/8 echo is there from the first turn (full at half), from about a third on the room joins (full at the top).	CC 22 **Space** as 1 Status quo	CC 23 **Space** as 1 Status quo	CC 24 **Space** as 1 Status quo	CC 25 —	CC 26 —	CC 27 —	CC 28 —
Row 3 Length	CC 29 **Length** 0 = short stab ↔ hits ring four times longer.	CC 30 **Length** as 1 Status quo	CC 31 **Length** as 1 Status quo	CC 32 **Length** as 1 Status quo	CC 33 —	CC 34 —	CC 35 —	CC 36 —
Fader Level	CC 5 **Level** keys: Steinway (VCSL) and Rhodes Mark I (jRhodes3d), as in track 009.	CC 6 **Level** as 1 Status quo	CC 7 **Level** as 1 Status quo	CC 8 **Level** as 1 Status quo	CC 9 —	CC 10 —	CC 11 —	CC 12 —
Button 1 Change	CC 37 **Change** 8 patterns: chain → shifted chain → pairs → 3-3-2 → Kerri syncope → Kerri riff → chain + shifted chain → chain + pairs.	CC 38 **Change** as 1 Status quo	CC 39 **Change** as 1 Status quo	CC 40 **Change** as 1 Status quo	CC 41 —	CC 42 —	CC 43 —	CC 44 —
Button 2 Sound	CC 45 **Sound** on / off: knobs = sound mix (piano → Rhodes, B3 → M1, vibes → marimba); fader = overtones; button 1 = nothing.	CC 46 **Sound** as 1; button 1 = echo throw while held (dotted 8th, long tail).	CC 47 **Sound** as 1; button 1 = push on / off (next chord on the last two 16ths).	CC 48 **Sound** as 1; button 1 = stutter while held (16ths, getting brighter).	CC 49 —	CC 50 —	CC 51 —	CC 52 —

Mode 2 — Drums + bass

	1	2	3	4	5	6 Drums	7 Bass	8
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 —
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 —	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 **Drums out** keys and bass alone while held.	CC 99 —	CC 100 —

Generated from `lab/keys/house-keys-lab-20.strudel` — edit the `@ctl` comments in the track, not this sheet.

Guide

What to listen for

Which job for the free button: does it help live (a move you would make in a set), does it sound good with the keys alone and with drums?

Harmony

Ein Akkord: Am9 in Kerri Chandler's shape. Wechsel: Am9 (2 bars) ↔ D9 (2 bars) as in track 009, D9 = F♯3 A3 C4 E4.