Launch Control XL 3 — Disco-Streicher 1 (lab/streicher, 009 Jonas 5–7: disco string figures from real sections)

Real string sections (SSO, CC Sampling Plus; VSCO 2, CC0); disco figures on the chords, not a pad.

Same four figures on every column; the columns differ only in the section sound.

Knob | Fader | Button | unused

Mode 16 — Candidates

	1 SSO violins	2 VSCO violins	3 Both	4 Dark	5	6	7	8
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (low-pass 1.5–14 kHz).	CC 14 **Brightness** as 1 SSO violins	CC 15 **Brightness** as 1 SSO violins	CC 16 **Brightness** as 1 SSO violins	CC 17 —	CC 18 —	CC 19 —	CC 20 —
Row 2 Space	CC 21 **Space** a little room at 0 ↔ hall and dotted-8th echo.	CC 22 **Space** as 1 SSO violins	CC 23 **Space** as 1 SSO violins	CC 24 **Space** as 1 SSO violins	CC 25 —	CC 26 —	CC 27 —	CC 28 —
Row 3 Build-up	CC 29 **Build-up** unison violins → + octave → + chord under the stabs → + scoops into the stabs.	CC 30 **Build-up** as 1 SSO violins	CC 31 **Build-up** as 1 SSO violins	CC 32 **Build-up** as 1 SSO violins	CC 33 —	CC 34 —	CC 35 —	CC 36 —
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 SSO violins	CC 7 **Level** as 1 SSO violins	CC 8 **Level** as 1 SSO violins	CC 9 —	CC 10 —	CC 11 —	CC 12 —
Button 1 Figure	CC 37 **Figure** echo stab (2 bars) → off-beat stabs → run + stab → falling on every beat.	CC 38 **Figure** as 1 SSO violins	CC 39 **Figure** as 1 SSO violins	CC 40 **Figure** as 1 SSO violins	CC 41 —	CC 42 —	CC 43 —	CC 44 —
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo.	CC 46 **Echo throw** as 1 SSO violins	CC 47 **Echo throw** as 1 SSO violins	CC 48 **Echo throw** as 1 SSO violins	CC 49 —	CC 50 —	CC 51 —	CC 52 —

Mode 2 — Context

	1	2	3	4	5 Progression	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009, following the progression.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Next** next progression (all 21), at the next 8-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 **Previous** previous progression, at the next 8-bar phrase.	CC 98 **Drums out** everything but the drums while held.	CC 99 —	CC 100 —

Guide

What to listen for

Warm, real, not cheesy? Which figure feels like a disco-house record? How far up can row 3 go?

Live

Row 3 builds from a thin violin line to the full section with scoops. Button 2 = echo throw.