Launch Control XL 3 — Disco-Gitarre 1 (lab/gitarre, 009 Jonas 5–7: real guitar strokes on our grid)

Every stroke is a real recording (Tele, CC BY 3.0 guitarelement; palm-mute, CC0 oceansonmars), cut and played on the 16th grid.

Same four rhythms on every column; the columns differ only in the guitar sound.

Knob Fader Button unused

Mode 16 — Candidates

	1 Tele ringing	2 Tele short	3 Palm-mute	4 Double	5	6	7	8
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (low-pass 800–9000 Hz).	CC 14 **Brightness** as 1 Tele ringing	CC 15 **Brightness** as 1 Tele ringing	CC 16 **Brightness** as 1 Tele ringing	CC 17 —	CC 18 —	CC 19 —	CC 20 —
Row 2 Space	CC 21 **Space** dry ↔ a 1/8 echo, then room.	CC 22 **Space** as 1 Tele ringing	CC 23 **Space** as 1 Tele ringing	CC 24 **Space** as 1 Tele ringing	CC 25 —	CC 26 —	CC 27 —	CC 28 —
Row 3 Density	CC 29 **Density** 0 = only the chord strokes ↔ muted ghost strokes on the 8ths ↔ the full 16th motor.	CC 30 **Density** as 1 Tele ringing	CC 31 **Density** as 1 Tele ringing	CC 32 **Density** as 1 Tele ringing	CC 33 —	CC 34 —	CC 35 —	CC 36 —
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Tele ringing	CC 7 **Level** as 1 Tele ringing	CC 8 **Level** as 1 Tele ringing	CC 9 —	CC 10 —	CC 11 —	CC 12 —
Button 1 Rhythm	CC 37 **Rhythm** off-beat (&) → Get Lucky → on the e → every third 16th.	CC 38 **Rhythm** as 1 Tele ringing	CC 39 **Rhythm** as 1 Tele ringing	CC 40 **Rhythm** as 1 Tele ringing	CC 41 —	CC 42 —	CC 43 —	CC 44 —
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo.	CC 46 **Echo throw** as 1 Tele ringing	CC 47 **Echo throw** as 1 Tele ringing	CC 48 **Echo throw** as 1 Tele ringing	CC 49 —	CC 50 —	CC 51 —	CC 52 —

Mode 2 — Context

	1	2	3	4	5 Progression	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009, following the progression.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Next** next progression (all 21), at the next 8-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 **Previous** previous progression, at the next 8-bar phrase.	CC 98 **Drums out** everything but the drums while held.	CC 99 —	CC 100 —

Guide

What to listen for

Warm and real enough? Tight on the beat? Which guitar sits best under the keys?

Live

Row 3 slowly up: from single chord stabs to the full 16th motor. Button 2 = echo throw.