Launch Control XL 3 — Melodie 3 (lab/melodie, 009 Jonas 4: real recorded wind phrases)

Columns 2–6: calm phrases cut from free improvisations, moved into A. They enter on the 1 of the phrase and play to their end.

Row 3 = how often: every 16 / 8 / 4 bars. Column 1 = the vibraphone of round 2, for comparison.

Knob | Fader | Button | unused

Mode 16 — Candidates

	1 Vibraphone	2 Trumpet A	3 Trumpet B	4 Trumpet C	5 Tenor sax	6 Flute	7	8
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (low-pass).	CC 14 **Brightness** as 1 Vibraphone	CC 15 **Brightness** as 1 Vibraphone	CC 16 **Brightness** as 1 Vibraphone	CC 17 **Brightness** as 1 Vibraphone	CC 18 **Brightness** as 1 Vibraphone	CC 19 —	CC 20 —
Row 2 Space / Soft	CC 21 **Soft** dry and short ↔ long notes, echo and room.	CC 22 **Space** echo and room (a little at 0).	CC 23 **Space** as 2 Trumpet A	CC 24 **Space** as 2 Trumpet A	CC 25 **Space** as 2 Trumpet A	CC 26 **Space** as 2 Trumpet A	CC 27 —	CC 28 —
Row 3 How often / Complexity	CC 29 **Complexity** core notes → figure → fills → doubles.	CC 30 **How often** every 16 · every 8 · every 4 bars.	CC 31 **How often** as 2 Trumpet A	CC 32 **How often** as 2 Trumpet A	CC 33 **How often** as 2 Trumpet A	CC 34 **How often** as 2 Trumpet A	CC 35 —	CC 36 —
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Vibraphone	CC 7 **Level** as 1 Vibraphone	CC 8 **Level** as 1 Vibraphone	CC 9 **Level** as 1 Vibraphone	CC 10 **Level** as 1 Vibraphone	CC 11 —	CC 12 —
Button 1 Phrase	CC 37 **Phrase** off-beat → tresillo → echo of the call, next bar.	CC 38 **Phrase** the next recorded phrase, from the next entry.	CC 39 **Phrase** as 2 Trumpet A	CC 40 **Phrase** as 2 Trumpet A	CC 41 **Phrase** as 2 Trumpet A	CC 42 **Phrase** as 2 Trumpet A	CC 43 —	CC 44 —
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo.	CC 46 **Echo throw** as 1 Vibraphone	CC 47 **Echo throw** as 1 Vibraphone	CC 48 **Echo throw** as 1 Vibraphone	CC 49 **Echo throw** as 1 Vibraphone	CC 50 **Echo throw** as 1 Vibraphone	CC 51 —	CC 52 —

Mode 2 — Context

	1	2	3	4	5 Progression	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009, following the progression.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Progression** next progression, at the next 8-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 **Drums out** everything but the drums while held.	CC 99 —	CC 100 —

Guide

What to listen for

Warm and alive, not mechanical? Which phrases still sound good the 4th time? Every 8 or every 4 bars?

Harmony

Mode 2 column 5 button 1 cycles the progression; phrases with F♯ / F skip the progressions they clash with.