Launch Control XL 3 — Disco-Streicher 2 (lab/streicher, 009 Jonas 5–7: big section, eight figures)

One sound on every column: SSO + VSCO sections together; one figure per column, all following the chords.

Button 1 = an octave lower (dark). Row 3 = build-up from a unison line to the full section.

Knob Fader Button unused

Mode 16 — Candidates

	1 Echo stab	2 Run up	3 Long run	4 Run down	5 Run + echo	6 Up and down	7 Swell	8 Pizzicato
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (low-pass 1.2–12 kHz).	CC 14 **Brightness** as 1 Echo stab	CC 15 **Brightness** as 1 Echo stab	CC 16 **Brightness** as 1 Echo stab	CC 17 **Brightness** as 1 Echo stab	CC 18 **Brightness** as 1 Echo stab	CC 19 **Brightness** as 1 Echo stab	CC 20 **Brightness** as 1 Echo stab
Row 2 Space	CC 21 **Space** room at 0 ↔ hall and dotted-8th echo.	CC 22 **Space** as 1 Echo stab	CC 23 **Space** as 1 Echo stab	CC 24 **Space** as 1 Echo stab	CC 25 **Space** as 1 Echo stab	CC 26 **Space** as 1 Echo stab	CC 27 **Space** as 1 Echo stab	CC 28 **Space** as 1 Echo stab
Row 3 Build-up	CC 29 **Build-up** unison line ⟶ + octave ⟶ + thirds / chord under it ⟶ + scoops into long notes.	CC 30 **Build-up** as 1 Echo stab	CC 31 **Build-up** as 1 Echo stab	CC 32 **Build-up** as 1 Echo stab	CC 33 **Build-up** as 1 Echo stab	CC 34 **Build-up** as 1 Echo stab	CC 35 **Build-up** as 1 Echo stab	CC 36 **Build-up** as 1 Echo stab
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Echo stab	CC 7 **Level** as 1 Echo stab	CC 8 **Level** as 1 Echo stab	CC 9 **Level** as 1 Echo stab	CC 10 **Level** as 1 Echo stab	CC 11 **Level** as 1 Echo stab	CC 12 **Level** as 1 Echo stab
Button 1 Register	CC 37 **Register** as written ↔ an octave lower (dark), from the next bar.	CC 38 **Register** as 1 Echo stab	CC 39 **Register** as 1 Echo stab	CC 40 **Register** as 1 Echo stab	CC 41 **Register** as 1 Echo stab	CC 42 **Register** as 1 Echo stab	CC 43 **Register** as 1 Echo stab	CC 44 **Register** as 1 Echo stab
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo.	CC 46 **Echo throw** as 1 Echo stab	CC 47 **Echo throw** as 1 Echo stab	CC 48 **Echo throw** as 1 Echo stab	CC 49 **Echo throw** as 1 Echo stab	CC 50 **Echo throw** as 1 Echo stab	CC 51 **Echo throw** as 1 Echo stab	CC 52 **Echo throw** as 1 Echo stab

Mode 2 — Context

	1	2	3	4	5 Progression	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009, following the progression.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Next** next progression (all 21), at the next 8-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 **Previous** previous progression, at the next 8-bar phrase.	CC 98 **Drums out** everything but the drums while held.	CC 99 —	CC 100 —

Guide

What to listen for

Which runs feel like disco house and not like an orchestra? Is the swell or the pizzicato useful?

Harmony

Mode 2 column 5 cycles the progression: the runs aim at the next chord's top note.