





IB Python API Lecture

Launch an EC2 Instance using Quantinsti-IB-API-Windows-Public-AMI

- Go to the Amazon website at <http://aws.amazon.com/> and login.
- After login, go to “Services” and click on “EC2 (Virtual Servers in the Cloud)”.



- Click “Launch Instance”.



- Choose Community AMIs and search for “Quantinsti-IB-API-Windows-Public-AMI”.

Step 1: Choose an Amazon Machine Image (AMI) Cancel and Exit

An AMI is a template that contains the software configuration (operating system, application server, and applications) required to launch your instance. You can select an AMI provided by AWS, our user community, or the AWS Marketplace; or you can select one of your own AMIs.

Quantinsti-IB-API-Windows-Public-AMI

AWS Launch Wizard for SQL Server offers an easy way to size, configure, and deploy Microsoft SQL Server Always On availability groups. Use AWS Launch Wizard for this launch?

Quick Start (0) My AMIs (1) AWS Marketplace (4008) **Community AMIs (1)**

Quantinsti-IB-API-Windows-Public-AMI - ami-0c176f1425480ba1f
 Quantinsti-IB-API-Windows-Public-AMI - created from windows server
 Root device type: ebs Virtualization type: hvm ENA Enabled: Yes

Select 64-bit (x86)

The following results for "Quantinsti-IB-API-Windows-Public-AMI" were found in other catalogs:

- 4008 results in AWS Marketplace

AWS Marketplace provides partnered Software that is pre-configured to run on AWS

- Choose an instance type. (t2.micro)

Step 2: Choose an Instance Type

Amazon EC2 provides a wide selection of instance types optimized to fit different use cases. Instances are virtual servers that can run applications. They have varying combinations of CPU, memory, storage, and networking capacity, and give you the flexibility to choose the appropriate mix of resources for your applications. [Learn more](#) about instance types and how they can meet your computing needs.

Filter by: All instance types Current generation Show/Hide Columns

Currently selected: t2.micro (Variable ECUs, 1 vCPUs, 2.5 GHz, Intel Xeon Family, 1 GiB memory, EBS only)

	Family	Type	vCPUs	Memory (GiB)	Instance Storage (GB)	EBS-Optimized Available	Network Performance
☒	General purpose	t2.micro Free tier eligible	1	1	EBS only	-	Low to Moderate
☐	General purpose	t2.small	1	2	EBS only	-	Low to Moderate
☐	General purpose	t2.medium	2	4	EBS only	-	Low to Moderate
☐	General purpose	t2.large	2	8	EBS only	-	Low to Moderate
☐	General purpose	m4.large	2	8	EBS only	Yes	Moderate
☐	General purpose	m4.xlarge	4	16	EBS only	Yes	High

Cancel Previous Review and Launch Next: Configure Instance Details

- Make Sure Auto-Assign Public IP is enabled

1. Choose AMI 2. Choose Instance Type 3. Configure Instance 4. Add Storage 5. Tag Instance 6. Configure Security Group 7. Review

Step 3: Configure Instance Details

Configure the instance to suit your requirements. You can launch multiple instances from the same AMI, request Spot instances to take advantage of the lower pricing, assign an access management role to the instance, and more.

Number of instances ⓘ 1

Purchasing option ⓘ ☐ Request Spot Instances

Network ⓘ vpc-08b34a6d (172.16.0.0/16) [Create new VPC](#)

Subnet ⓘ subnet-ce82d0e6 (172.16.0.0/24) | us-east-1c [Create new subnet](#)
249 IP Addresses available

Auto-assign Public IP ⓘ **Enable**

Domain join directory ⓘ None [Create new directory](#)

IAM role ⓘ None [Create new IAM role](#)

Shutdown behavior ⓘ Stop

Enable termination protection ⓘ ☐ Protect against accidental termination

Monitoring ⓘ ☐ Enable CloudWatch detailed monitoring
Additional charges apply.

Tenancy ⓘ Shared tenancy (multi-tenant hardware)
Additional charges will apply for dedicated tenancy.

[Cancel](#) [Previous](#) [Review and Launch](#) [Next: Add Storage](#)

- Add Storage (Free Tier can go upto 30 GB). Click on Add Tags

Step 4: Add Storage

Your instance will be launched with the following storage device settings. You can attach additional EBS volumes and instance store volumes to your instance, or edit the settings of the root volume. You can also attach additional EBS volumes after launching an instance, but not instance store volumes. [Learn more](#) about storage options in Amazon EC2.

Volume Type	Device	Snapshot	Size (GiB)	Volume Type	IOPS	Throughput (MB/s)	Delete on Termination	Encrypted
Root	/dev/sda1	snap-0527c12b3a6505f2f	30	General Purpose SSD (GP2)	100 / 3000	N/A	☒	Not Encrypted

[Add New Volume](#)

Free tier eligible customers can get up to 30 GB of EBS General Purpose (SSD) or Magnetic storage. [Learn more](#) about free usage tier eligibility and usage restrictions.

[Cancel](#)
[Previous](#)
[Review and Launch](#)
[Next: Add Tags](#)

- Add a Tag, Key = Name, Value=<any> and click on “Configure Security Group”

1. Choose AMI 2. Choose Instance Type 3. Configure Instance 4. Add Storage 5. Add Tags 6. Configure Security Group 7. Review

Step 5: Add Tags

A tag consists of a case-sensitive key-value pair. For example, you could define a tag with key = Name and value = Webserver.

A copy of a tag can be applied to volumes, instances or both.

Tags will be applied to all instances and volumes. [Learn more](#) about tagging your Amazon EC2 resources.

Key (128 characters maximum)	Value (256 characters maximum)	Instances	Volumes
Name	qi-ibapi-windows-server	☒	☒

[Add another tag](#) (Up to 50 tags maximum)

[Cancel](#)
[Previous](#)
[Review and Launch](#)
[Next: Configure Security Group](#)

- Configure Security Group. Allow incoming (Inbound) traffic on port 3389 (RDP)

1. Choose AMI 2. Choose Instance Type 3. Configure Instance 4. Add Storage 5. Add Tags 6. Configure Security Group 7. Review

Step 6: Configure Security Group

A security group is a set of firewall rules that control the traffic for your instance. On this page, you can add rules to allow specific traffic to reach your instance. For example, if you want to set up a web server and allow Internet traffic to reach your instance, add rules that allow unrestricted access to the HTTP and HTTPS ports. You can create a new security group or select from an existing one below. [Learn more](#) about Amazon EC2 security groups.

Assign a security group: ☒ Create a new security group
☐ Select an existing security group

Security group name:

Description:

Type	Protocol	Port Range	Source	Description
RDP	TCP	3389	Custom 0.0.0.0/0	e.g. SSH for Admin Desktop

Add Rule

Warning

Rules with source of 0.0.0.0/0 allow all IP addresses to access your instance. We recommend setting security group rules to allow access from known IP addresses only.

Cancel Previous **Review and Launch**

- Review and Launch

▸ Instance Details [Edit instance details](#)

▸ Storage [Edit storage](#)

▸ Tags [Edit tags](#)

Cancel Previous **Launch**

- View Instances

- [How to connect to your Windows instance](#)
- [Amazon EC2: Microsoft Windows Guide](#)
- [Learn about AWS Free Usage Tier](#)
- [Amazon EC2: Discussion Forum](#)

While your instances are launching you can also

- [Create status check alarms](#) to be notified when these instances fail status checks. (Additional charges may apply)
- [Create and attach additional EBS volumes](#) (Additional charges may apply)
- [Manage security groups](#)

View Instances