


Changing the Instance type after Creation of EC2 Instance.

Steps to Change Instance Type (t3.micro → something else)

1. Go to **Amazon EC2** console
2. Select your **running instance**
3. Click **Instance state**
4. Click **Stop instance**
5. Wait until instance status becomes **stopped**
6. Click **Actions** → **Instance settings** → **Change instance type**
7. Select new type (example: t3.small, t3.medium, etc.)
8. Click **Apply**
9. Start the instance again

After stopping the instance we can change the instance type.



Then we have to select the another instance type.

aws

Search

[Alt+S]

United States (N. Virginia)

Dhanam M (0517-4104-1276)

EC2 > Instances > i-0c32fe9e602b3d0e9 > Change instance type

Change instance type

[info](#) | [Get advice](#)

You can change the instance type only if the current instance type and the instance type that you want are compatible.

Instance ID

i-0c32fe9e602b3d0e9 (linux)

Current instance type

t3.micro

New instance type

t3.small

Only free plan eligible instance types with x86 (32-bit) / (64-bit) architecture can be chosen.

☒ EBS-optimized

EBS-optimized is enabled by default for this instance type.

Instance type comparison

Attribute	t3.micro	t3.small
On-Demand Linux pricing	0.0104 USD per Hour	0.0208 USD per Hour
On-Demand Windows pricing	0.0196 USD per Hour	0.0392 USD per Hour
vCPUs	2 (1 core)	2 (1 core)
Memory (MiB)	1024	2048
Storage (GB)	-	-
Supported root device types	ebs	ebs

The instance type has been changed successfully.

aws

Search

[Alt+S]

United States (N. Virginia)

Dhanam M (0517-4104-1276)

EC2 > Instances

EC2

Dashboard

AWS Global View

Events

Instances

Instance Types

Launch Templates

Spot Requests

Savings Plans

Instances (1/1)

Last updated less than a minute ago

Find instance by attribute or tag (case-sensitive)

All states

	Name	Instance ID	Instance state	Instance type	Status check	Alarm status	Availability Zone	Public IPv4
☒	linux	i-0c32fe9e602b3d0e9	Stopped	t3.small	-	View alarms	us-east-1f	-