

# MIS-FreeFlying



Welcome and thank you for supporting MIS-FreeFlying!

# Contents

1. [Quick Start](#)
2. [Setup](#)
3. [Upgrade](#)
4. [Contacts Information](#)

# 1. Quick Start

## 1. API Compatibility Level

Edit – Project Settings – Player – Other Settings

### ■ Unity 2019/2020

Api Compatibility Level\* .NET 4.x ▼

### ■ Unity 2021

Api Compatibility Level\* .NET Framework ▼

## 2. Setup Sequence

- Post-Process (Optional)
- INVECTOR
- MIS
- MIS-FreeFlying

## 3. Demo Scene

Find Assets/MIS-Packages/FreeFlying/Demo/.

#### 4. Play

| Control                                         | Input                                   | API                                          |
|-------------------------------------------------|-----------------------------------------|----------------------------------------------|
| Start Flying                                    | Space while holding down                | EnterActionState(bool)                       |
| Finish Flying / Hard-Landing                    | LEFT CTRL                               | ExitActionState()<br>EnterHardLandingState() |
| Strafe mode toggle                              | TAB                                     |                                              |
| Immediate Sprint mode toggle                    | LEFT SHIFT while holding down LEFT CTRL | StartSprintImmediately()<br>FinishSprint()   |
| Sprint mode toggle with Multi Sprint Count > 0  | LEFT SHIFT                              | Sprint(bool)                                 |
| Sprint mode toggle with Multi Sprint Count == 0 | LEFT SHIFT                              | Sprint(bool)                                 |
| Sprint mode toggle (None Use Continuous Sprint) | LEFT SHIFT while holding down LEFT CTRL | Sprint(bool)                                 |
| Slow mode toggle                                | Holding Down LEFT ALT                   | SetSlowMode(bool)                            |
| Escape action while Free/Strafe mode            | Q + WASD                                | -                                            |
| Sprint Roll while Sprint mode                   | A / D / W                               | -                                            |
| Moving while Free/Strafe/Slow mode              | WASD                                    | -                                            |
| Moving Up/Down while Free/Slow mode             | Mouse /<br>LEFT CTRL (Down), SPACE (Up) | -                                            |
| Moving Up/Down while Strafe/Slow mode           | LEFT CTRL (Down), SPACE (Up)            | -                                            |
| Moving while Sprint/Slow mode                   | Auto Moving Forward                     | -                                            |
| Rotating while Free/Strafe/Sprint/Slow mode     | Mouse                                   | -                                            |

NOTE: Every input key can be modified via Inspector. Some of input key can be replaced via relevant APIs.

**NOTE: In Sprint mode, the character moves forward automatically so that the player does not have to hold down WASD keys. WAD keys are used for Sprint Rolling action.**

## Additional Controls

### 1) Flying Section

#### ■ Auto Cancel Flying

If it is enabled, FreeFlying will be automatically canceled,

- When the character reaches the ground by given value, Ground Distance Min.
- When the character crashes obstacles while Sprint mode.

#### ■ Jump Up for Flying

This feature only works when the character starts flying from the ground. If the character starts flying in the air the character status transits to flying mode immediately.

#### ■ Sprint Stamina

Basically MIS-FreeFlying consumes the Sprint Stamina which is set on `mvThirdPersonController`. If it is greater than 0, the consumption will increase accordingly. If you would like not to consume Stamina at all while Sprint, the value must be set less than minus double amount of Sprint Stamina because it consumes in every frame on `vThirdPersonController`.

### 2) Movement Section

#### ■ Stop Move Speed

Even though the player release move key the character does not stop immediately. The higher this value, the faster the character stops.

#### ■ Slow Mode Multiplier

The lower this value, the slower the character moves while holding down LEFT ALT key.

#### ■ Multi-Sprint

If Multi Sprint Count Origin is set to greater than 0, the character can Sprint the amount of times of this value. Multi Sprint Speed Multiplier value will multiply the current Sprint speed either. For example, if this value is set to 2, the second Sprint speed will be double.

#### ■ Idle Animation

MIS-FreeFlying has 4 types of Flying Idle animation clips.

- Idle in Free mode (if Random Idle Time Origin is set greater than 0, it will randomly changes Idle animation)
- Idle in Strafe mode (Idle animation is not changed)
- Idle while holding a weapon

### **3) Damage Section**

#### ■ No Damage On Action

If it is enabled, the character will not have any damage while MIS-FreeFlying action.

#### ■ Active Ragdoll On Sprint Crash

If it is enabled, the character may transits to Ragdoll mode when he/she hits the obstacles.

#### ■ Crash Angle

Set crash able angle between Min and Max. Cur value is the crash angle when the character hits.

## 2. Setup & Tutorials

### 1. Overall

MIS Package Setup usually proceeds as following tasks when this package needs:

- Replaces Invector components with MIS's.

If MIS controller and input manager are already installed, this step will be skipped.

- Adds Animator Parameters

If MIS Animator Parameters are already added, this step will be skipped.

- Generates Animator StateMachine / States

If the relevant Animator Layers/StateMachines/States are already added, each step will be skipped.

Any Animator layouts of this package setup are automatically arranged.

- Adds MIS Package components and extra settings such as VFX.

If the relevant components or extra settings are already installed, this step will be skipped.

- Sometimes MIS Setup modifies components default value to fix any problem. Please see the console log.

You can run this setup repeat on the same character although the character already has been set up.

## 2. mvFreeFlying

Mv Free Flying Shooter (Script)

**MISFREEFLYING SHOOTER**

Close Properties

Script 

mvFreeFlyingShooter

Input

Flying

Movement

Damage

Events

Debug

ChainedAction

**Flying Conditions**

Auto Cancel Flying ☐

Obstacle Layer Mask 

Default

Ground Distance Min 

0.15

 Max 

100

 Cur 

0

Auto Draw Hide Weapon ☒

Capsule Collider Center Or X 

0

 Y 

1.1

 Z 

0

**Jump Up for Flying**

Fly Jump Up Power 

3

Fly Jump Up Distance 

1.5

Fly Jump Up Period Origin 

1

 Currer 

1

**Stamina**

Stamina 

2

Sprint Stamina 

0

Escape Stamina 

10

Sprint Roll Stamina 

10

Stamina Recovery Delay 

2.5

**Flying Escape**

Use Flying Escape Root M ☒

Flying Escape Speed Multi 

2


**Flying SprintRoll**

Use Flying Sprint Roll Root ☒

Flying Sprint Roll Speed M 

2


### 3. mvWindForce




### 4. WindForceVFX




### 5. mvWindForceTarget




## 6. Animator



<Basic/Melee/Shooter>



<Melee/Shooter>



<Melee/Shooter>

7. [MIS YouTube](#)

## 3. Upgrade

Please refer to Release History section in store page whenever this package gets upgrade.

The upgrade proceeds when any of the following occurs:

- Invector/MIS upgrade
- Bug fix or feature upgrade itself
- Compatibility with other MIS Package releases

**IMPORTANT: Should check that packages with dependencies are released.**

**IMPORTANT: Check the Asset Store's Release History whether or not you should remove the old version.**

**IMPORTANT: Keep the install sequence with dependencies.**

The character does not move at normal speed or does not move at all.

Cause

Investor Update v2.6.4

#1 Update MIS to v2.7.12+

#2 In Investior v2.6.4a, MIS-FreeFlying condition must be added to ApplyMovementConditions() in vThirdPersonMotor.cs, but it is not declared as virtual. Therefore, you must manually add virtual as follows.

```
public virtual bool ApplyMovementConditions()
```

#3 Find the same API in mvThirdPersonMotor.cs and remove the comment as follows.

Uncomment the followings:

```
/* <= Remove this line  
// Please uncomment it after adding virtual in the base method  
public override bool ApplyMovementConditions()  
{  
  
    ...  
  
}  
*/ <= Remove this line
```

## 4. Contacts Information

Please contact us through the following channels:

- Email: [mymobilin@gmail.com](mailto:mymobilin@gmail.com)
- Discord: <https://discord.gg/CXrbdUNetc> (Recommended)

**IMPORTANT: INVECTOR Company is not responsible for management for this asset**



Make Game Better