



LabVIEW Python Bridge Server Side Code



PyTestFlow Custom Sequence Code




The image shows a code editor interface with a file explorer on the left and a code editor on the right. The file explorer shows a project named 'PyTestFlowDemo' with several subfolders and files. The file 'lv_call_sequence.py' is selected. The code editor shows the content of 'lv_call_sequence.py', which includes imports for 'TestSequence', 'numeric_limit_step', 'pass_fail_step', and 'labview'. It also defines a function 'get_vcore_from_labview()' and a decorator '@numeric_limit_step' for a function 'measure_vcore()'. The function 'measure_vcore()' calls 'get_vcore_from_labview()' and returns its result. The decorator '@pass_fail_step' is also shown, but its function is not fully visible.

```
test_sequences > lv_call_sequence.py > get_vcore_from_labview

1  from pytestflow.core.sequence import TestSequence
2  from pytestflow.steps.numeric_limit import numeric_limit_step
3  from pytestflow.steps.pass_fail import pass_fail_step
4  from jki_python_bridge_for_labview import labview as lv
5
6
7  def get_vcore_from_labview():|
8      try:
9          lv.connect()
10         result = lv.example.add(167, 2)
11         lv.disconnect()
12         return result
13     except Exception as e:
14         return e
15
16 @numeric_limit_step(name="measure_vcore", limit=(1.0, 1.3), mode="between")
17 def measure_vcore():
18     return get_vcore_from_labview()
19
20 @pass_fail_step(name="functional_check")
21 def functional_check():
22     return True
```

PyTestFlow Custom Sequence Selection



PyTestFlow Custom Sequence Start run

127.0.0.1:8001

sequential_model ▾

Open Sequence File

Start run

Stop

Pause

Inter-step delay (ms) 5

Open Last Report

PTF
PYTESTFLOW

▼ BasicSequence

Setup (vuoto)

▼ Main

measure_vcore {"Output": 169.0, "limit": [1.0, 1.3], "mode": "between"} numeric_limit

functional_check {"Output": true} pass_fail

Cleanup (vuoto)

PyTestFlow Custom Sequence Report

Test Sequence Report - SN: 123

Failed

Generated: 2026-05-03_20-54-42
Message: Test Sequence LabVIEW_Call_Sequence failed
State Type: StateType.COMPLETED
Steps: 2 total - 1 passed / 1 failed / 0 done / 0 other

Summary

#	Step	Status	State	Subsequence
001	measure_vcore	Failed	StateType.COMPLETED	No
002	functional_check	Passed	StateType.COMPLETED	No

Contents

- [0 - Test Sequence Report - SN: 123](#)
- [0.1 - measure_vcore](#)
- [0.2 - functional_check](#)

Details

0 - Test Sequence Report - SN: 123

Failed

PyTestFlow State: PyTestFlowFailed **Prefect State:** StateType.COMPLETED **Message:** Test Sequence LabVIEW_Call_Sequence failed

Step Details