

Write a self-contained 61131-3 structured text function block that reads diagnostic data from a Profibus DP slave device.



To create a self-contained IEC 61131-3 structured text function block that reads diagnostic data from a Profibus DP slave device, you need to follow the structure and syntax for IEC 61131-3 programming languages. Here is an example of a function block for reading diagnostic data using Structured Text:

```
Copy code
iecst
FUNCTION_BLOCK ReadProfibusDiagnostics
VAR_INPUT
 ProfibusMaster : REFERENCE TO PROFIBUS_MASTER;
 SlaveAddress : BYTE;
END_VAR
VAR_OUTPUT
 DiagnosticData: ARRAY [0..255] OF BYTE;
                : BOOL;
 Status
 ErrorMessage : STRING;
END_VAR
VAR
 ReqState : INT := 0;
 InternalStatus : BOOL;
END_VAR
METHOD ReadDiagnosticData: BOOL
VAR
 DiagnosticTelegram : ARRAY [0..255] OF BYTE;
 TelegramLength : UDINT;
                    : UDINT;
END_VAR
CASE ReqState OF
0: (* Initialize *)
 ProfibusMaster^.Initialize();
 ReqState := 10;
10: (* Request diagnostic data *)
 InternalStatus := ProfibusMaster^.ReadDiagnostic(SlaveAddress, Diagnostic
 IF InternalStatus THEN
    FOR i := 0 TO TelegramLength - 1 DO
     DiagnosticData[i] := DiagnosticTelegram[i];
    END_FOR;
   Status := TRUE;
    ErrorMessage := '';
    RETURN TRUE;
 ELSE
   Status := FALSE;
    ErrorMessage := ProfibusMaster^.LastError;
    RETURN FALSE;
 END_IF;
END_CASE;
END_METHOD
END_FUNCTION_BLOCK
```

In this example, a function block `ReadProfibusDiagnostics` is created with the necessary input and output variables. The input variables are a reference to a Profibus DP master device (`ProfibusMaster`) and the address of the slave device (`SlaveAddress`). The output variables include an array of bytes containing the diagnostic data (`DiagnosticData`), a status flag (`Status`), and an error message (`ErrorMessage`).

The function block contains a method `ReadDiagnosticData` that implements the reading of diagnostic data from the Profibus DP slave device using a state machine approach. The state machine has two states: an initialization state (0) and a state to request diagnostic data (10).

In the initialization state (0), the Profibus DP master device is initialized. After initialization, the state machine moves to the state 10, where it sends a request for diagnostic data using the `ReadDiagnostic` method from the `ProfibusMaster` object. If the request is successful, the received diagnostic data is copied to the output array `DiagnosticData`, the status flag is set to TRUE, and the error message is cleared. Otherwise, the status flag is set to FALSE, and the error message is populated with the latest error from the Profibus DP master device.

This example assumes the existence of a `profibus\_MASTER` object with the necessary methods and properties. You may need to adapt this example to fit the







specific Profibus DP master library you are using.