Traffic Simulator

User Manual

March 15, 2026

Contents

1 About **1**

2 Simulation **1**
2.1 Maps 1

3 Settings Menu **1**

4 Simulation Visuals **2**
4.1 Live Statistics 2
4.2 Playback Controls 2

5 Statistics **2**

1 About

This document describes how to use Traffic Simulator . The software was developed as part of the course System- och programvaruutveckling (DT117G) at Örebro University.

2 Simulation

Traffic Simulator uses a simulation model based on the Nagel-Schreckenberger traffic simulation model. The model uses discrete time, and hence moves in textbfsteps or textbfticks.

2.1 Maps

The following maps are implemented*

- **One way street**: A simple one way street. The first map made for this simulator.
- **T Intersection**: A one way street with a connecting one way street in the middle.
- **Highway**: Simple highway with two lanes in each direction. Overtakes are implemented, to allow faster driving vehicles to pass slower driving ones.
- **Autobahn**: A large highway with five lanes in each direction. Supports overtakes in all lanes, and outer lanes has an extra speed up, to ensure the overtaking car does not get stuck in the outer lane.

*more will be added in the future, as well as the possibility to create custom maps.

3 Settings Menu

1. **Map selector** Select the map, or scenario, to run a simulation on (see section 2.1 on page 1).
2. **Road length** Set the number of cells in the main road. Only applicable to certain maps. Also note the scaling of vehicles may be very small for large values.
3. **Offline simulation toggle** Allows for running simulations without visuals, and get the statistics summary at the end. Useful for large simulations since it greatly speeds up the simulation time.
4. **Min speed** Set the minimum ideal speed on vehicles.

5. **Max speed** Set the maximum ideal speed on vehicles.
6. **Number of ticks** Only active when running offline simulations. This decides for how long the simulation will run.
7. **Spawn rate** Set the chance of a vehicle spawning each tick.
8. **Time scaling** Set the initial time scaling for the simulation. Not active for offline mode.
9. **Start simulation** Start a new simulation with the current settings.
10. **Exit program** Quit to desktop.

4 Simulation Visuals

4.1 Live Statistics

4.2 Playback Controls

5 Statistics