

Blender → Godot Export Add-on (v3 – Object Settings Patch)

Overview

This add-on streamlines exporting assets from Blender to Godot with clean scene structure, collision setup, and optional per-object configuration.

It is designed for **clarity, consistency, and teaching workflows**, especially when building game-ready assets.

Core Concepts

There are **two levels of control**:

1. Scene Settings (Global Defaults)

Controls how the exported `.tscn` scene is structured.

2. Object Settings (Optional Overrides)

Lets individual objects define their own physics and collision behavior.

Default Behavior (Important)

Out of the box, the add-on uses:

- **Scene Root Node:** `Node3D`
- **Scene Body:** `No Body`
- **Batch Export:** Uses per-object settings (enabled)

This means:

The scene is just a container, and objects define their own behavior.

Scene Settings Panel

Location

Found in the export panel.

Options

Root Node

- Default: `Node3D`
- Defines the root of the exported Godot scene
- **Always active**, even when using per-object settings

Use Object Settings (Checkbox)

When enabled:

- Scene-level Body and Collision options are hidden
- Each object controls its own physics setup
- **Does NOT affect the scene root node**

When disabled:

- Scene-level Body and Collision are applied to all objects

Body

(Only visible when **Use Object Settings is OFF**) (Only visible when **Use Object Settings is OFF**)

Options:

- No Body (default)
- `StaticBody3D`
- `RigidBody3D`
- `CharacterBody3D`

Collision Shape

(Only visible when **Use Object Settings is OFF**)

Defines the collision shape applied to objects.

Object Settings Panel

Location

Object Properties → Godot Export section

Workflow

Step 1: Select a "Source" Object

Set up:

- Body type
- Collision shape

Step 2: Copy Settings

Select other objects, then click:

Copy From Selected

This copies the active object's settings to all selected objects.

Step 3: Remove Settings (Optional)

Click:

Remove Settings

This clears per-object overrides and returns the object to scene defaults.

Batch Export Panel

Use Per-Object Settings (from Object panel)

Default: ON

When enabled:

- Each object uses its own assigned settings

When disabled:

- Scene settings override everything
-

Recommended Workflow (Best Practice)

For Game Development

1. Leave **Use Object Settings ON**
2. Keep Scene Body = `No Body`
3. Assign bodies/collisions per object

This results in:

- Clean Godot scenes
 - Flexible object behavior
 - Easier debugging
-

For Simple Props / Static Scenes

1. Turn **Use Object Settings OFF**
2. Set Scene Body (e.g., `StaticBody3D`)
3. Export

This is faster for:

- Environment props
 - Non-interactive assets
-

Design Philosophy

This add-on follows a few key rules:

- **Predictable scene structure** → Always uses `Node3D` as root when needed
 - **Separation of concerns** → Scene = container, Objects = behavior
 - **Blender-native language** → "Copy From Selected" instead of custom terminology
 - **Minimal setup friction** → Smart defaults reduce required clicks
-

Tips

- Use one object as a "template" and copy settings from it
 - Keep collision simple (Box/Convex) for performance
 - Avoid mixing scene-level and object-level settings unless necessary
-

Troubleshooting

Objects exporting without collision

- Ensure:
- Object has settings assigned
- OR Scene settings are enabled

Scene looks empty in Godot

- Check export path
- Confirm objects are enabled for export

Wrong physics type in Godot

- Verify whether **Use Object Settings** is enabled

Summary

Feature	Recommended Setting
Scene Root	Node3D
Scene Body	No Body
Use Object Settings	ON
Batch Export	Use Per-Object Settings

This setup gives you the most control with the least confusion.

If you want further improvements (auto-naming, LOD export, collision preview, etc.), those can be layered on top of this system cleanly.