

VPN Setup Guide

Overview

This guide explains how to set up and connect to the Acme Corp VPN for secure remote access to company resources.

Prerequisites

- Company-issued laptop with administrator access.
- Internet connection (minimum 25 Mbps download, 5 Mbps upload).
- MFA device or authenticator app (Microsoft Authenticator or similar).

Installation

Windows

1. Open the Company Portal app (pre-installed on company laptops).
2. Search for “Acme VPN Client” and click “Install.”
3. Follow the installation wizard. Click “Yes” when prompted for administrator access.
4. Once installed, restart your laptop.

macOS

1. Open Self Service (pre-installed on company laptops).
2. Search for “Acme VPN Client” and click “Install.”
3. Follow the installation prompts.
4. Once installed, restart your Mac.

Linux

Contact IT Support for Linux VPN setup instructions.

Configuration

First-Time Setup

1. Open the Acme VPN Client (search for “AcmeVPN” in the Start menu or Applications folder).
2. Click “Add Connection” and enter:
 - **Server Address:** vpn.acmecorp.com
 - **Port:** 443
 - **Protocol:** IKEv2
3. Click “Save.”
4. Enter your company credentials (email@acmecorp.com and password).
5. Complete MFA authentication via your registered device.
6. Click “Connect.”

Connecting

Daily Use

1. Open the Acme VPN Client.
2. Click the connection profile “Acme Corp VPN.”
3. Enter credentials if not saved.
4. Complete MFA prompt.
5. Wait for “Connected” status.

Quick Connect (Tray Icon)

- Windows: Right-click the VPN icon in the system tray → “Connect.”
- macOS: Click the VPN icon in the menu bar → “Connect.”

Disconnecting

- Open the VPN client and click “Disconnect.”
- Or use the tray/menu icon to disconnect.

Troubleshooting

Cannot Connect

Issue	Solution
“Server not found”	Check internet connection. Ensure vpn.acmecorp.com is correct.
Authentication failed	Verify credentials. Reset password if needed at password.acmecorp.com.
MFA not working	Contact IT to reset MFA configuration.
Connection timeout	Try a different network. Some public Wi-Fi blocks VPN ports.

Slow Connection

- Use a wired Ethernet connection instead of Wi-Fi.
- Close bandwidth-intensive applications.
- Connect to a network with at least 50 Mbps speed.

Split Tunneling

By default, only company traffic (internal sites, file servers, email) goes through the VPN. Regular internet traffic uses your local connection. To change this setting:

1. Open VPN Client → Settings.

2. Under “Split Tunneling,” select “Route all traffic through VPN” (not recommended unless required).

Security Reminders

- Never share your VPN credentials.
- Always disconnect from VPN when not in use.
- Do not use public or unsecured Wi-Fi without VPN.
- Report lost or stolen devices immediately to IT.
- The VPN automatically disconnects after 8 hours of inactivity for security.

Contact

- IT Portal: it.acmecorp.com
- IT Support: extension 4200
- Email: it-support@acmecorp.com

Document Version 2.0 — Last Updated February 2026