



ORACLE
NetSuite

Costed Bill of Materials



2025.2

December 17, 2025



Copyright © 2005, 2025, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, and MySQL are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

If this document is in public or private pre-General Availability status:

This documentation is in pre-General Availability status and is intended for demonstration and preliminary use only. It may not be specific to the hardware on which you are using the software. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to this documentation and will not be responsible for any loss, costs, or damages incurred due to the use of this documentation.

If this document is in private pre-General Availability status:

The information contained in this document is for informational sharing purposes only and should be considered in your capacity as a customer advisory board member or pursuant to your pre-General Availability trial agreement only. It is not a commitment to deliver any material, code, or functionality, and should not be relied upon in making purchasing decisions. The development, release, timing, and pricing of any features or functionality described in this document may change and remains at the sole discretion of Oracle.

This document in any form, software or printed matter, contains proprietary information that is the exclusive property of Oracle. Your access to and use of this confidential material is subject to the terms and conditions of your Oracle Master Agreement, Oracle License and Services Agreement, Oracle PartnerNetwork Agreement, Oracle distribution agreement, or other license agreement which has been executed by you and Oracle and with which you agree to comply. This document and information contained herein may not be disclosed, copied, reproduced, or distributed to anyone outside Oracle without prior written consent of Oracle. This document is not part of your license agreement nor can it be incorporated into any contractual agreement with Oracle or its subsidiaries or affiliates.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <https://www.oracle.com/corporate/accessibility>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Sample Code

Oracle may provide sample code in SuiteAnswers, the Help Center, User Guides, or elsewhere through help links. All such sample code is provided "as is" and "as available", for use only with an authorized NetSuite Service account, and is made available as a SuiteCloud Technology subject to the SuiteCloud Terms of Service at www.netsuite.com/tos.

Oracle may modify or remove sample code at any time without notice.

No Excessive Use of the Service

As the Service is a multi-tenant service offering on shared databases, Customer may not use the Service in excess of limits or thresholds that Oracle considers commercially reasonable for the Service. If Oracle reasonably concludes that a Customer's use is excessive and/or will cause immediate or ongoing performance issues for one or more of Oracle's other customers, Oracle may slow down or throttle Customer's excess use until such time that Customer's use stays within reasonable limits. If Customer's particular usage pattern requires a higher limit or threshold, then the Customer should procure a subscription to the Service that accommodates a higher limit and/or threshold that more effectively aligns with the Customer's actual usage pattern.

Beta Features

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

This documentation is in pre-General Availability status and is intended for demonstration and preliminary use only. It may not be specific to the hardware on which you are using the software. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to this documentation and will not be responsible for any loss, costs, or damages incurred due to the use of this documentation.

The information contained in this document is for informational sharing purposes only and should be considered in your capacity as a customer advisory board member or pursuant to your pre-General Availability trial agreement only. It is not a commitment to deliver any material, code, or functionality, and should not be relied upon in making purchasing decisions. The development, release, and timing of any features or functionality described in this document remains at the sole discretion of Oracle.

This document in any form, software or printed matter, contains proprietary information that is the exclusive property of Oracle. Your access to and use of this confidential material is subject to the terms and conditions of your Oracle Master Agreement, Oracle License and Services Agreement, Oracle PartnerNetwork Agreement, Oracle distribution agreement, or other license agreement which has been executed by you and Oracle and with which you agree to comply. This document and information contained herein may not be disclosed, copied, reproduced, or distributed to anyone outside Oracle without prior written consent of Oracle. This document is not part of your license agreement nor can it be incorporated into any contractual agreement with Oracle or its subsidiaries or affiliates.

Table of Contents

Costed Bill of Materials	1
Installing Costed Bill of Materials	1
Prerequisites for Installing Costed Bill of Materials	1
Creating or Customizing Roles and Permissions to Use Costed Bill of Materials	2
Supported Browsers for Costed Bill of Materials	4
Creating Costed Bill of Materials	5
Material Costs Subtab	7
Top Level Costs Subtab	9
Fully Exploded Costs Subtab	11
Cost Types for Material Cost Calculation	12
Per Costing Method	13
Per Purchase Price	14
Per Item Default	14
Conversion Cost Calculations for Top Level Costs and Fully Exploded Costs Subtabs	14

Costed Bill of Materials

The Costed Bill of Materials SuiteApp calculates the total cost of an assembly based on a bill of materials revision, manufacturing routing, and cost templates used. The cost is calculated by adding up the costs of the components.

The SuiteApp also enables you to do the following:

- View the comprehensive cost breakdown of an assembly item, including bills of materials, operations, and cost types based on selected bill of materials revision.
- View and analyze the costs of each component needed for an assembly, including material and conversion costs for each component.
- Estimate the potential costs of manufacturing assembly items for bill of materials based on costing method, purchase price, and item default price.
- Access cost breakdowns for bills of materials as part of your product engineering and costing processes.

You can access the SuiteApp by navigating to Reports > Cost Accounting > Costed Bill of Materials.

 **Note:** The cost calculations are not based on planned standard cost, cost re-evaluation, or cost roll-up values for any standard cost assembly item.

Watch the following help video for an overview of the Costed Bill of Materials SuiteApp:

 [Costed Bill of Materials SuiteApp Overview](#)

Installing Costed Bill of Materials

The Costed Bill of Materials SuiteApp requires a NetSuite OneWorld account.

Only users with Administrator role can install the SuiteApp. For more information about installing a SuiteApp, see the help topics [Installing from the SuiteApp Marketplace](#) and [SuiteApp Marketplace in NetSuite](#).

Prerequisites for Installing Costed Bill of Materials

To use the Costed Bill of Materials SuiteApp, enable the features in the following table. For more information, see the help topic [Enabling Features](#).

To work with subsidiaries, you need access to a NetSuite One World account and have enabled Subsidiaries. To learn more, see the help topic [Working with Subsidiaries](#).

Subtab	Feature Name
Items & Inventory	Advanced Bill of Materials
	Assembly Items
SuiteCloud	Custom Records
	Server SuiteScript
	Client SuiteScript
	SuiteCloud Development Framework

- Note:** Following are some general information for the Costed Bill of Materials SuiteApp:
- The currency of the cost displayed in the report is shown based on the default currency of the selected subsidiary.
 - The subassemblies should have a master default bill of materials and the default routing for location to get the detailed estimated cost.
 - The SuiteApp displays details in the **Materials Costs, Top Level Costs, and Fully Exploded Costs** subtabs irrespective of whether a work center, cost template, or routing is active or inactive.
 - The SuiteApp supports up to 900 levels of assembly items and up to 400 sub-assemblies in each level.

Creating or Customizing Roles and Permissions to Use Costed Bill of Materials

If you are an administrator, you can create new roles or customize roles for using the Costed Bill of Materials SuiteApp. For more information, see the help topics [Assigning Roles to an Employee](#) and [Customizing or Creating NetSuite Roles](#).

A custom role **Costed_BOM_Role** is created during the SuiteApp installation which will be used as a default value for **Execute As Role** field in the Script Deployment page. It is updated in the **Costed Bill of Materials** and **Costed BOM DataService** script.

Refer to the following table for minimum access levels of permissions required for SuiteApp deployments. These minimum permissions must be updated to the existing role or while creating a new role.

Permissions	Minimum Access Level
Lists > Bill of Materials	View
Lists > CRM Groups	View
Lists > Custom Record Entries	Full
Lists > Documents and Files	View
Lists > Items	View
Lists > Locations	View
Lists > Perform Search	View
Lists > Subsidiaries	View
Lists > Units	View
Lists > Vendors	View
Setup > Accounting Lists	View
Setup > Custom Record Types	Full
Setup > Enable Features	Full

Permissions	Minimum Access Level
Setup > SuiteScript	View
Setup > SuiteScript Scheduling	Full
Setup > Set Up Company	Full
Custom Record > Costed BOM MR Assembly Instances	Full

Refer to the following table for the minimum permissions required for logged-in user role.

Permissions	Minimum Access Level
Lists > Bill of Materials	View
Lists > Items	View
Lists > Subsidiaries	View
Lists > Locations	View
Lists > Documents and Files	View
Lists > Manufacturing Routing	View
 Note: This permission is required only if the Manufacturing Routing and Work Center feature is enabled.	

 **Note:** The currency and unit symbols are displayed in the three subtabs (**Material Costs**, **Top Level Costs**, and **Fully Exploded Costs**). The symbols are displayed irrespective of the currency and unit permissions given to the logged-in user.

Enabling Manufacturing Routing And Work Center Feature

When **Manufacturing Routing And Work Center** feature is enabled in the **Enable Features** page after the SuiteApp is installed, you must perform the following steps.

To enable Manufacturing Routing And Work Center feature:

1. Go to Setup > User/Roles > Manage Roles.
2. On the **Costed_BOM_Role** role row, click **Customize**. The Role page opens.
3. Create a custom role.
 - a. (Optional) To rename the custom role, enter the role name in the **Name** field.
 - b. In the **Permissions** subtab, click the **Lists** subtab.
 - c. In a new row, select **Manufacturing Cost Template**.
 - d. From the level list, select **View**.
 - e. Click **Add**.
 - f. From the list, select **Manufacturing Routing**.
 - g. From the level list, select **View**.
 - h. Click **Save**.
4. Add the custom role to the scripts:

- a. Go to Customization > Scripting > Scripts.
- b. On the **Costed Bill of Materials** script row, click **Deployments**.
- c. On the Script Deployments page, click **Edit**.
- d. In the **Execute As Role** field, select the custom role that you created in step 3.
- e. Click **Save**.
- f. Repeat steps 4.1 to 4.5 for **Costed BOM DataService** script.

Enabling Multiple Currency Feature

When **Multiple Currencies** feature is enabled in the **Enable Features** page after the SuiteApp is installed, you must perform the following steps.

To enable Multiple Currency feature:

1. Go to Setup > User/Roles > Manage Roles.
2. On the **Costed_BOM_Role** role row, click **Customize**. The Role page opens.
3. Create a custom role.
 - a. (Optional) To rename the custom role, enter the role name in the **Name** field.
 - b. In the **Permissions** subtab, click the **Lists** subtab.
 - c. In a new row, select **Currency**.
 - d. From the level list, select **View**.
 - e. Click **Add**.
 - f. Click **Save**.
4. Add the custom role to the scripts:
 - a. Go to Customization > Scripting > Scripts.
 - b. On the **Costed Bill of Materials** script row, click **Deployments**.
 - c. On the Script Deployments page, click **Edit**.
 - d. In the **Execute As Role** field, select the custom role that you created in step 3.
 - e. Click **Save**.
 - f. Repeat steps 4.1 to 4.5 for **Costed BOM DataService** script.

Supported Browsers for Costed Bill of Materials

The Costed Bill of Materials SuiteApp supports the following browsers and operating systems:

Browser	Operating System
Google Chrome	Windows 10
	Mac OS 10.15 or newer
Microsoft Edge (Chromium-based)	Windows 10
Mozilla Firefox	Windows 10
	Mac OS 10.15 or newer
Safari	Mac OS 10.15 or newer

Note: In the **Item** field of the Costed Bill of Materials page, type three characters and click on the field for the items to be populated in the list, based on the search. This is applicable only for Safari browser.

Creating Costed Bill of Materials

The Costed Bill of Materials SuiteApp displays the total cost breakdown of an assembly item using the bill of materials revision, routing steps, and costing method.

To create a costed bill of materials:

1. Go to Reports > Cost Accounting > Costed Bill of Materials.
2. From the **Subsidiary** list, select a subsidiary for the bill of materials.
3. From the **Item** list, select the assembly item for which you want the bill of materials.
4. From the **Location** list, select a location to view data for that location.
5. From the **Bill of Materials** list, select the bill of materials to automatically populate the **Bill of Materials Revision** and **Effective Date** fields.
6. From the **Display Control** list, select either **By Date** or **By Revision** to decide what to include in an assembly. This field is available only when an assembly item uses revision control for its effective display control value.
7. The **Date/Effective Date** field displays the date used to decide when a component should be included in an assembly. This field is available only when an assembly item uses revision control for its effective **display control** value.

The field is editable only if the **display control** value is set to **By Date**. The **Date** field controls which date is used when querying the components of the assembly item. Then, components are shown based on the following criteria:

- The selected date is greater than or equal to the effective start date.
 - The selected date is less than or equal to the effective end date.
8. From the **Bill of Materials Revision** field, choose the bill of materials revision from the list.
 9. Check the **By Manufacturing Routing** box only if the assembly item has an associated routing. The box will be disabled if the item has no associated routing.

Note: You must check the **By Manufacturing Routing** box to see data in **Top Level Costs** and **Fully Exploded Costs** subtabs.

10. From the **Manufacturing Routing** list, select a manufacturing routing. This field is enabled when you check the **By Manufacturing Routing** box.
11. In the **Build Quantity** field, enter the build quantity of the item you want to see for the costed bill of materials. The default value is 1. However, if **Manufacturing Routing And Work Center** feature is enabled in **Enable Features** page, the default value will be the costing lot size mentioned in selected assembly item record.
12. Check the **Top Level Only** box to limit the details to the selected assembly item, its components, and operation only. Information about sub-assemblies is not displayed. Clear this box to display details at all levels of the fully exploded Bill of Materials. This field cannot be checked if the **By Manufacturing Routing** box is selected.

Note: If the **Top Level Only** field is checked, the costs for the selected assembly item are sourced directly from the assembly item.

If the **Top Level Only** field is not checked, the costs for the selected assembly item are sourced and aggregated from the component items in the exploded bill of materials.

13. From the **Material Cost** list, you can select the cost type to be used for all components. For more information, see [Cost Types for Material Cost Calculation](#).

14. Click **Submit**.

You can view the three subtabs (**Material Costs**, **Top Level Costs**, and **Fully Exploded Costs**) after the process is complete.

15. (Optional) You can download the report by clicking the **Download** button.

Note: Following points are applicable to the downloaded file in the SuiteApp.

- The downloaded file has the file name in the format **Assembly Name_BOM name_Revision name_Routing name_timestamp.xls** with a character limit of 199 characters. If **Assembly Name_BOM name_Revision name_Routing name** is of 170 characters, the SuiteApp will automatically truncate the characters and allocate the remaining characters for **_timestamp.xls**.
- The file name will add the display name as a part of the assembly name if the **Show Display Name with Item Codes** preference is enabled.
- Unsupported characters (\, /, :, *, ?, ", <, >, |, %) will be converted to underscore (_) in the file name.

16. (Optional) To email the report, click the **Email** button which goes to a new browser tab.
 - a. In the **Email Recipients** field, enter the email addresses. By default, the field contains the email address of the logged-in user.

Note: Following points are applicable to the email option in the SuiteApp.

- The email addresses in the **Email Recipients** field must be separated by commas.
- You can add a maximum of 10 email recipients in the **Email Recipients** field.
- You cannot email the Costed Bill of Materials report if the file size is more than 10 MB. So, you can download the report and email it instead.

- b. Click **Submit**.

17. (Optional) To simulate the report with modified unit cost (for non-assembly items) and build quantity values:

- a. In the **Unit Cost** column of the **Material Costs** subtab, modify the value for any nonassembly item.
 - b. In the **Simulate Build Quantity** field of the **Material Costs** subtab, modify the value for which you want to generate a simulated report.

Note: The **Build Quantity** field value in the **Filters** section takes up the value provided in the **Simulate Build Quantity** field after simulation. However, the modified values will not be reflected in the original report.

- c. Click **Simulate** to display the simulated Costed Bill of Materials report.
- d. To download the simulated report, click the **Download** button.

This Costed Bill of Materials report shows the modified values in all subtabs based on the updated unit cost of the nonassembly items.

Note: Following points are applicable to the simulate option in the SuiteApp:

- The modified changes of the simulated report will be replaced with the original values after clicking the **Submit** button.
- The modified unit cost is updated in each bill of materials where the item is used if:
 - The unit cost is modified for any nonassembly item.
 - The item is used in more than one bill of materials within the exploded bill of materials for the assembly.
- When the values are modified in the **Unit Cost** column of the **Material Costs** subtab, the values are highlighted in blue color.
- The downloaded file has the file name in the format **Assembly Name_BOM name_Revision name_Routing name_simulated_timestamp.xls** with a character limit of 199 characters. If **Assembly Name_BOM name_Revision name_Routing name** exceeds 170 characters, the SuiteApp automatically truncates the excess characters and allocates the remaining characters for **simulated_timestamp.xls**.

Material Costs Subtab

The **Material Costs** subtab provides a breakdown of the cost of the components used in the assembly. You can view material costs based on item costing method, purchase price, or item default price on this subtab. Using these details, you analyze the cost of the materials used in the assembly.

The following table provides details about the fields in the **Material Costs** subtab.

Field	Description
Total Material Cost	Total material cost calculates based on the build quantity and cost of the end assembly item.
Material Cost per Unit	Material cost of a single unit of the end assembly item.

The following table provides details about the columns in the **Material Costs** subtab.

Column Name	Description
Item Name	Component item name.

Column Name	Description
Level	Level represents the level in the hierarchy of the exploded bill of materials.
Item Display Name	Display name of the component item.
Quantity	Quantity of the component item as per the bill of materials required to produce one unit of the assembly at this level.
Component Yield	Component yield is retrieved from the selected bill of materials revision of the assembly item.
Quantity Per Assembly	Quantity of the component item required to produce one unit of the assembly at this level based on component yield.
Quantity Per Top Level Assembly	Quantity of the component item required to produce one unit of the end assembly.
Quantity for Build	Quantity for Build calculates based on the product of build quantity and quantity per top level assembly.
Unit Cost	Unit cost of the component as per the selected material cost source. This column can be edited to generate simulated reports. For more information, read step 17 in Creating Costed Bill of Materials .
Units	Consumption unit of the component.
Total Cost	Total cost of the component.

Note: The SuiteApp selects the bill of materials revision for a subassembly in the following precedence order:

1. If a BOM contains multiple revisions, the active revision is considered based on the current date falling within the effective start and end date range.
2. If a BOM contains multiple revisions with the effective date range as expired or future effective, the BOM revision with latest or last modified date is considered.

Inactive BOM revisions are not considered for estimations.

Following points show how the bill of materials is associated with an effective revision of a subassembly:

- A BOM associated with the **Default for Location** field is prioritized over the BOM mapped to the **Master Default** field.
- If a subassembly is not mapped to a BOM that is associated with **Default for Location** field, the BOM mapped to **Master Default** field is considered.
- Inactive BOM is not considered even if it is associated with **Default for Location** or **Master Default** fields.
- If there are multiple BOMs with multiple revisions, and revisions have expired or future effective dates, the BOM revision associated with **Default for Location** field is considered.
- If a subassembly is mapped to following BOMs, the **Master Default** BOM with active revision is considered.
 - BOM that contains multiple revisions with expired or future effective date and associated to **Default for Location** field.
 - BOM with active revision and mapped to the **Master Default** field.

Top Level Costs Subtab

The **Top Level Costs** subtab provides a breakdown of the costs of the assembly by cost type. You can view and analyze cost breakdown for manufacturing operations on this subtab. The details can help you understand the cost of each manufacturing operation involved in producing the item.

The following table provides details about the fields in the **Top Level Costs** subtab.

Field	Description
Total Assembled Cost	Total assembled cost calculates based on the sum of material cost and conversion cost of the end assembly item.

Field	Description
Assembled Cost per Unit	Assembled cost of a single unit of the end assembly item.

The following table provides details about the columns in the **Top Level Costs** subtab.

Column Name	Description
Operation	The sequence of the operation in the routing.
Operation Name	Name of the operation sequence.
Item Name	Component item name.
Material Costs	Cost of materials as per the selected material cost source to produce the final assembly.
Labor Run	Cost of labor run to produce the final assembly.
Labor Run Overhead	Cost of labor overhead to produce the final assembly.
Labor Setup	Cost of labor setup to produce the final assembly.
Labor Setup Overhead	Cost of labor setup overhead to produce the final assembly.
Machine Run	Cost of machine run to produce the final assembly.
Machine Run Overhead	Cost of machine run overhead to produce the final assembly.
Machine Setup	Cost of machine setup to produce the final assembly.
Machine Setup Overhead	Cost of machine setup overhead to produce the final assembly.
Total Cost	Total cost to produce the final assembly.

For more information about the conversion cost calculations for top level costs, see [Conversion Cost Calculations for Top Level Costs and Fully Exploded Costs Subtabs](#).

Note: The following information is applicable to both **Top Level Costs** and **Fully Exploded Costs** subtabs:

- When a subassembly is not associated with a default routing, the conversion cost is populated as 0. This calculation is based on the unavailability of a default routing for the subassembly. The conversion cost will remain 0 even if there are other routing options for the subassembly, but are not marked as default.
- The assembly item is displayed with the conversion cost when the following two conditions are true:
 - The subassembly does not have any component in the revision.
 - Default routing is associated with the item.

The material cost will be 0 and on expanding the assembly item, no components will be displayed.
- The assembly item displays conversion cost as zero when the following two conditions are true:
 - The subassembly does not have an effective bill of materials or revision.
 - Default routing is associated with the item.
- If a **Operation** is not defined for a component in the **Component Per Operation** subtab of a routing record, the first operation will be considered for that component.

Fully Exploded Costs Subtab

The **Fully Exploded Costs** subtab provides a detailed breakdown of material and operation costs by cost types on this subtab. You can analyze the costs associated with each material and operation used in the assembly.

The following table provides details about the fields in the **Fully Exploded Costs** subtab.

Field	Description
Total Exploded Cost	Total exploded cost is calculated based on the sum of material cost and conversion cost of all subassemblies of the end assembly item.
Exploded Cost per Unit	Exploded cost of a single unit of the end assembly item.
Material Cost %	Percentage of the material cost from the total exploded cost percentage.
Conversion Cost %	Percentage of the conversion cost from the total exploded cost percentage.

The following table provides details about the columns in the **Fully Exploded Costs** subtab.

Column Name	Description
Item Name	Component item name.
Level	Level represents the level in the hierarchy of the exploded bill of materials.

Column Name	Description
Material Costs	Cost of materials as per the selected material cost source to produce the final assembly.
Conversion Costs	Cost types associated with each assembly to produce the final assembly.
Labor Run	Cost of labor run to produce the final assembly.
Labor Run Overhead	Cost of labor overhead to produce the final assembly.
Labor Setup	Cost of labor setup to produce the final assembly.
Labor Setup Overhead	Cost of labor setup overhead to produce the final assembly.
Machine Run	Cost of machine run to produce the final assembly.
Machine Run Overhead	Cost of machine run overhead to produce the final assembly.
Machine Setup	Cost of machine setup to produce the final assembly.
Machine Setup Overhead	Cost of machine setup overhead to produce the final assembly.
Total Cost	Total cost to produce the final assembly.

For more information about the conversion cost calculations for fully exploded costs, read [Conversion Cost Calculations for Top Level Costs and Fully Exploded Costs Subtabs](#).

Cost Types for Material Cost Calculation

You can select the cost type from the **Material Cost** field in the Costed Bill of Materials page.

Following are the cost types.

- [Per Costing Method](#)
- [Per Purchase Price](#)
- [Per Item Default](#)



Note: Following information is applicable to all cost types:

- Item purchase price values are converted to the currency of the selected subsidiary.
- Service, non-inventory, or charge items do not have any costing method associated with them. So, the value of these items is retrieved from item purchase price. For currency conversion, currency exchange rates values are used.
- If an assembly item is not associated with a bill of materials or bill of materials revision, then the costs for the assembly item will be sourced the way the inventory items are sourced.
- You will see blank conversion cost values if the values for conversion costs are not defined in the cost template. Some examples for conversion costs are labor setup, machine run, and so on.

Watch the following help video for cost calculation methods:

 Cost Calculation Methods

Per Costing Method

Cost is calculated based on the costing method assigned to the item. For example: LIFO, FIFO, standard, average, and so on.

The costs are sourced from the items in the sequence outlined in the table. For example, refer to row 1 in the below table. An assembly item will source by item location average cost if the value is greater than 0. Else, it moves to the next source (item location last purchase price) and checks if the value is greater than 0. It then goes to the next source (Item purchase price) and checks if the value is greater than 0. If none of the source types provide a value greater than 0, then the price of the assembly item will be 0.

 **Note:** If the **Top Level Only** field is not checked, the costs for the assembly item are sourced and aggregated from the component items in the exploded bill of materials.

Item Type	Top Level	Costing Method	Cost Source
Assembly item or inventory item	Yes	Group Average Average	1. Item location average cost 2. Item location last purchase price 3. Item purchase price
		Standard	1. For assembly item, the cost is a summation of component item cost. For inventory item, the cost is based on item location standard cost. 2. Item location average cost 3. Item location last purchase price 4. Item purchase price
		Lot Numbered Specific Actual FIFO LIFO, and so on.	1. For assembly item, the cost is a summation of component item cost. For inventory item, the cost is based on item location default cost. 2. Item location average cost 3. Item location last purchase price 4. Item purchase price
Inventory item	No	Group Average Average	1. Item location average cost 2. Item location last purchase price 3. Item purchase price
		Standard	1. Item location default cost 2. Item location average cost 3. Item location last purchase price 4. Item purchase price
		Lot Numbered Specific Actual	1. Item location default cost 2. Item location average cost 3. Item location last purchase price 4. Item purchase price

Item Type	Top Level	Costing Method	Cost Source
		FIFO	
		LIFO, and so on.	

Per Purchase Price

Cost is calculated as per the last purchase price of the item (assembly item or inventory item) in the location based on top level selection. If the last purchase price is not available, the report uses the default item purchase price.

Per Item Default

Cost is calculated as per the standard cost of the item in the location. This cost type is not displayed in the **Material Cost** list if the **Standard Costing** feature is disabled.

Conversion Cost Calculations for Top Level Costs and Fully Exploded Costs Subtabs

The following table contains formulas and criteria based on which the conversion cost for top level costs and fully exploded items costs subtabs are calculated:

Cost Calculation	Criteria	Formula
Labor Run and Labor Run Overhead		Cost * Labor Resources * (Run Rate/60) * Quantity for build
Labor Setup and Labor setup Overhead	if (Quantity for build < Costing Lot Size)	Cost * Labor Resources * (Setup Time/60)* (Quantity for Build / Costing Lot Size)
Labor Setup and Labor setup Overhead	if (Quantity for build > Costing Lot Size)	Cost * Labor Resources * (Setup Time/60)
Machine Run and Machine Run Overhead		Cost * Machine Resources * (Run Rate/60) * Quantity for build
Machine Setup and Machine Setup Overhead	if (Quantity for build < Costing Lot Size)	Cost * Machine Resources * (Setup Time/60)* (Quantity for build / Costing Lot Size)
Machine Setup and Machine Setup Overhead	if (Quantity for build > Costing Lot Size)	Cost * Machine Resources * (Setup Time/60)

 **Note:** Quantity for build is calculated by considering the base unit (unit of measure) of the .

The following table contains details of where the formula values are retrieved from:

Formula Component	Retrieved From
Cost	Manufacturing Cost Template page
Labor Resources	Manufacturing Routing page

Formula Component	Retrieved From
Machine Resources	Manufacturing Routing page
Setup Time	Manufacturing Routing page
Run Rate	Manufacturing Routing page
Costing Lot Size	Item Location Configuration page
Quantity for build	Product of quantity per top level assembly and build quantity.

The following calculations for conversion costs are applied for the phantom assemblies:

- Conversion costs are not calculated for phantom assemblies that are labelled as subassemblies under a main assembly.
- On the **Fully Exploded Costs** subtab, if the selected main assembly is phantom with associated manufacturing routing, the SuiteApp calculates the conversion cost for phantom assembly. However, if the phantom is a subassembly of the selected main assembly, the SuiteApp does not calculate the conversion cost.
- If phantom is a subassembly, the associated conversion cost is not included in the cost setup of the main assembly. The SuiteApp calculates and includes the conversion costs only when the phantom is labelled as main assembly.

For example:

The main assembly has a conversion cost of \$100, whereas the phantom assembly has a conversion cost of \$20 according to its manufacturing routing. In this case:

- When you run Costed BOM process for main assembly, the results show total conversion cost as \$100. In this case, phantom conversion cost is not calculated. This conversion cost value of \$100 is shown on the **Fully Exploded Costs** subtab.
- When you run Costed BOM process for phantom assembly, the result shows total conversion cost as \$20. In this case, phantom conversion cost is calculated, since the SuiteApp considers it as an end assembly. This conversion cost value of \$20 is shown on the **Fully Exploded Costs** subtab.

 **Note:** For an assembly that is labelled as a subassembly under the phantom subassembly breakdown, the conversion cost for that assembly is zero.

Watch the following help video for cost calculation methods:

 [Cost Calculation Methods](#)