

```
admin@ip-10-0-1-40: ~
Archivo  Editar  Ver  Buscar  Terminal  Ayuda
GNU nano 8.4 /etc/vsftpd.conf
listen=YES
#
# This directive enables listening on IPv6 sockets. By default, listening
# on the IPv6 "any" address (:::) will accept connections from both IPv6
# and IPv4 clients. It is not necessary to listen on *both* IPv4 and IPv6
# sockets. If you want that (perhaps because you want to listen on specific
# addresses) then you must run two copies of vsftpd with two configuration
# files.
listen_ipv6=NO
#
# Allow anonymous FTP? (Disabled by default).
anonymous_enable=YES
anon_root=/var/ftp
no_anon_password=YES
#
# Uncomment this to allow local users to log in.
local_enable=NO
#
# Uncomment this to enable any form of FTP write command.
write_enable=NO
userlist_file=/etc/vsftpd.userlist
userlist_enable=NO
userlist_deny=NO
#
# Default umask for local users is 077. You may wish to change this to 022,
# if your users expect that (022 is used by most other ftpd's)

^G Help      ^O Write Out ^F Where Is  ^K Cut       ^T Execute   ^C Location
^X Exit      ^R Read File ^\ Replace   ^U Paste     ^J Justify   ^_ Go To Line
```

```
admin@ip-10-0-1-40: ~
Archivo  Editar  Ver  Buscar  Terminal  Ayuda
admin@ip-10-0-1-40:~$ ftp 54.87.215.189
Connected to 54.87.215.189.
220 (vsFTPd 3.0.5)
Name (54.87.215.189:admin): anonymous
230 Login successful.
Remote system type is UNIX.
Using binary mode to transfer files.
ftp> exit
221 Goodbye.
admin@ip-10-0-1-40:~$ ftp 54.87.215.189
Connected to 54.87.215.189.
220 (vsFTPd 3.0.5)
Name (54.87.215.189:admin): ftpuser
530 This FTP server is anonymous only.
ftp: Login failed
ftp> exit
221 Goodbye.
admin@ip-10-0-1-40:~$
```