

```
admin@ip-10-0-1-40: ~
GNU nano 8.4 /etc/vsftpd.conf
# Capabilities.
#
# Run standalone? vsftpd can run either from an inetd or as a standalone
# daemon started from an initscript.
listen=YES
#
# This directive enables listening on IPv6 sockets. By default, listening
# on the IPv6 "any" address (:::) will accept connections from both IPv6
# and IPv4 clients. It is not necessary to listen on *both* IPv4 and IPv6
# sockets. If you want that (perhaps because you want to listen on specific
# addresses) then you must run two copies of vsftpd with two configuration
# files.
listen_ipv6=NO
#
# Allow anonymous FTP? (Disabled by default).
anonymous_enable=NO
#
# Uncomment this to allow local users to log in.
local_enable=YES
#
# Uncomment this to enable any form of FTP write command.
write_enable=YES
userlist file=/etc/vsftpd.userlist
userlist_enable=YES
userlist_deny=NO
#
# Default umask for local users is 077. You may wish to change this to 022,
# if your users expect that (022 is used by most other ftpd's)
#local_umask=022
^G Help      ^O Write Out  ^F Where Is   ^K Cut        ^T Execute    ^C Location   M-U Undo      M-A Set Mark
^X Exit      ^R Read File  ^_ Replace    ^U Paste      ^J Justify    ^_ Go To Line M-B Redo      M-C Copy
```

```
admin@ip-10-0-1-40: ~
GNU nano 8.4 /etc/vsftpd.userlist *
ftpuser

```

```
admin@ip-10-0-1-40: ~  
Archivo  Editar  Ver  Buscar  Terminal  Ayuda  
admin@ip-10-0-1-40:~$ ftp 54.87.215.189  
Connected to 54.87.215.189.  
220 (vsFTPD 3.0.5)  
Name (54.87.215.189:admin): ftpuser  
331 Please specify the password.  
Password:  
230 Login successful.  
Remote system type is UNIX.  
Using binary mode to transfer files.  
ftp> exit  
221 Goodbye.  
admin@ip-10-0-1-40:~$ ftp 54.87.215.189  
Connected to 54.87.215.189.  
220 (vsFTPD 3.0.5)  
Name (54.87.215.189:admin):  
530 Permission denied.  
ftp: Login failed  
ftp> exit  
221 Goodbye.  
admin@ip-10-0-1-40:~$
```