

IT Support of XF

2025 Oct

1. Production-Line Application

Refer to this section for installing Production applications of every Production Line.

1.1. Installation Guidelines

- Identify your production area in the Application Reference Table below.
- Click the appropriate Installation Link.
- Download and run the setup.exe installer.
- Follow on-screen prompts to complete installation.
- Verify printer connection using the static IP listed for your area.

1.2. Important Configuration Notes

- Do not manually add printers.
- All label printers use static IP addresses.
- Only update IP if printer hardware has been replaced.

1.3 Application Reference Table

Section	Area	Label Printer IP (Large)	Label Printer IP (Small)	Installation Link
Coextrusion	COEX	172.17.30.91		appprod.inteplast.com - /appProduction/XF/CoExtrusion/
Spiral-Cut	Spiral-Cut	172.17.30.92		appprod.inteplast.com - /appProduction/XF/SpiralCut/
Stretch-Lamination	Stretch-Lamination	172.17.30.93		appprod.inteplast.com - /appProduction/XF/StretchLamination/
G-Lamination	G-mination	172.17.30.94		appprod.inteplast.com - /appProduction/XF/GLaminator/
Slitting	HA 12&13	172.17.30.167	172.17.31.65	appprod.inteplast.com - /appProduction/XF/Slitting/
Slitting	HA 14	172.17.30.97	172.17.30.96	appprod.inteplast.com - /appProduction/XF/Slitting/
Slitting	HA 15	172.17.30.98	172.17.30.98	appprod.inteplast.com - /appProduction/XF/Slitting/
Shipping	Shipping	172.17.30.55		appprod.inteplast.com - /appProduction/XF/Schedule/
Edge-Lamination	Edge-Lamination	172.17.30.103	172.17.30.102	appprod.inteplast.com - /appProduction/XF/EdgeLamination/
Printing & VF	Printing & VF	172.17.30.101	172.17.30.100	appprod.inteplast.com - /appProduction/XF/Printing/

1.4 Installation Visual Guide

Directory Path:

<https://appprod.inteplast.com/appProduction/XF/>

Steps:

- Select The correct application folder
- Follow below image for visual step-by-step instructions on downloading the application **setup.exe** file





Figure 1-1: Downloading and Keep the Application. Setup File - Demonstrates how to click the link to download and keep the setup.exe file.

- Follow below image for visual step-by-step instructions on running the application **setup.exe** file



Figur 1-2: Running the Application Setup File - Demonstrates how to run the downloaded setup.exe file.

2. IT Support for Office

2.1. Access Permission of XF's NAS

IT only have access to the "Software" folder on the XF Network Attached Storage (NAS).

Directory Path of XF's NAS:

NAS Path: \\172.17.25.100\

Username: cyber

Password: softwareteam

2.2. New Computer Setup

When setting up a new computer in the XF Office, complete the following installations:
(include Anti-Virus, AS400,)

1.1.1. Install the Anti-Virus

Directory Path:

<\\172.17.25.100\Software\Cyber\WPJK Anti-Virus\>

Steps:

- I. Navigate to the path above.
- II. Locate the file cmd.bat.
- III. Run the **cmd.bat** batch file to install the antivirus software.

Name	Date modified	Type	Size
 cmd.bat	10/30/2024 3:55 PM	Windows Batch File	1 KB
 WindowsSensor.MaverickGyr.exe	10/30/2024 3:55 PM	Application	156,730 KB

Figure 2-1: Running the Batch File – Double click the cmd.bat batch file to install the Anti-Virus.

1.1.2. Install the steps of new AS400

Directory Path:

\\172.17.25.100\Software\Cyber\AS400 (New Version) \

Installation Steps:

- a) Run **jre1.8.0_26164** (Java Runtime) located in the directory above.
- b) Navigate to the folder:
IBM ACS Client → Files → Windows_Application.
- c) Choose the correct installer based on your system architecture:
 - For 32-bit systems: **install_acs_32_allusers**
 - For 64-bit systems: **install_acs_64_allusers**




Figure 2-2: Running the AS400 install File - Demonstrates how to find and select the install_acs_32_allusers or install_acs_64_allusers file.

d) After install the AS400, please copy the "FPCTX.hod" icon and paste to the user's desktop.

Directory Path:

[\\172.17.25.100\Software\Cyber\AS400 \(New Version\) \IBM ACS Client\Files](\\172.17.25.100\Software\Cyber\AS400 (New Version) \IBM ACS Client\Files) FPCTX.hod

Steps:

please copy and paste the "FPCTX.hod" file to the user's desktop.




Figure 2-3: Copy and paste the FPCTX.hod File - Demonstrates locate the FPCTX file, select it, and copy and paste it to the user's desktop.

1.1.3.Plant Management for Supervisor

Directory Path:

<https://appprod.inteplast.com - /appProduction/XF/PlantMgt/>

Installation Instructions:

Follow the same installation steps as outlined for the **Production Line Applications**.

1.1.4.Product line Scheduling(For Feifei Chou only)

Directory Path:

<https://appprod.inteplast.com/appProduction/XF/Scheduling/>

Installation Instructions:

Use the same procedure as described in the Production Line Applications installation section.

1.2. IT Support For TEO phone.

The TEO 4101 phone some time need update the server address: **97.75.243.226**

If you need change the personnel information from the TEO phone, please send the email to Brandon Crow / Inteplast Lolita Administration <bcrow@inteplast.com>

If you have the hardware issue. Please send the email to Joe Hamm

ghamm@inteplast.com

The following map shows the exact location of Joe Hamm's office.



Figure 2-4: Map of Joe Hamm's Office Location - A map with a red arrow indicating the entrance to Joe Hamm's office, used to guide the delivery of old phone hardware.

3. Install and connect the Kyocera printer for office user

3.1. Download and install the printer's driver and connect the printer from the Kyocera web site.

https://youtu.be/F_pz6BIsRXY

3.1.1. If you are first time to connect the Kyocera printer, you should be downloaded the driver from Kyocera web site.

https://www.kyoceradocumentsolutions.com/download/index_en.html?r=0

Select your country from the Kyocera download center.




Figure 3-1: Kyocera Driver Download Page - Select Country - Screenshot of the Kyocera Document Solutions website's driver download page, prompting the user to select the country first.

3.1.2. Check the Brand/Model/IP address and Hostname



Figure 3-2: Check Printer Brand, model and IP address - Physical image of the printer, with a red box highlighting the information on the printer.



Figure 3-3: Check Printer Brand - Physical image of the printer, with a red box highlighting the Brand on the printer.



Figure 3-4: Check Printer Model - Physical image of the printer, with a red box highlighting the model information on the printer label.




Figure 3-4: Check Printer IP Address and Hostname - Physical image of the printer, with a red box highlighting the IP address and hostname on the printer label.

6.1.XF network topology:




Figure 6.1: XF Network Topology Diagram - XF facility network topology diagram containing yellow fiber-optic links and blue Ethernet connections.

6.2.XF network physical map:

