







Command Prompt

Cisco Packet Tracer PC Command Line 1.0

C:\>ping 172.16.2.10

Pinging 172.16.2.10 with 32 bytes of data:

Reply from 172.16.2.10: bytes=32 time=2ms TTL=125

Reply from 172.16.2.10: bytes=32 time=14ms TTL=125

Reply from 172.16.2.10: bytes=32 time=14ms TTL=125

Reply from 172.16.2.10: bytes=32 time=3ms TTL=125

Ping statistics for 172.16.2.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 2ms, Maximum = 14ms, Average = 8ms

C:\>

C:\>ping 10.2.2.10

Pinging 10.2.2.10 with 32 bytes of data:

Reply from 10.2.2.10: bytes=32 time=8ms TTL=125

Reply from 10.2.2.10: bytes=32 time=2ms TTL=125

Reply from 10.2.2.10: bytes=32 time=2ms TTL=125

Reply from 10.2.2.10: bytes=32 time=2ms TTL=125

Ping statistics for 10.2.2.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 2ms, Maximum = 8ms, Average = 3ms

R0#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/24 is subnetted, 1 subnets

O 10.2.2.0/24 [110/65] via 20.1.1.2, 00:01:36, Serial0/1/1

20.0.0.0/8 is variably subnetted, 2 subnets, 2 masks

C 20.1.1.0/24 is directly connected, Serial0/1/1

L 20.1.1.1/32 is directly connected, Serial0/1/1

100.0.0.0/8 is variably subnetted, 2 subnets, 2 masks

C 100.1.1.0/24 is directly connected, Serial0/1/0

L 100.1.1.1/32 is directly connected, Serial0/1/0

R0#

00:04:24: %OSPF-5-ADJCHG: Process 1, Nbr 2.2.2.2 on Serial0/1/0 from LOADING to FULL, Loading Done

```
R0#show ip ospf neighbor
```

Neighbor ID	Pri	State	Dead Time	Address	Interface
3.3.3.3	0	FULL/ -	00:00:33	20.1.1.2	Serial0/1/1
2.2.2.2	0	FULL/ -	00:00:30	100.1.1.2	Serial0/1/0

R0#

PC1

Physical Config **Desktop** Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 10.2.2.10

Subnet Mask 255.255.255.0

Default Gateway 10.2.2.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::230:A3FF:FE9D:CE72

Default Gateway

DNS Server

PC0

Physical Config **Desktop** Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 172.16.2.10

Subnet Mask 255.255.0.0

Default Gateway 172.16.2.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R2
R2(config)#interface serial0/1/0
R2(config-if)#ip address 20.1.1.2 255.255.255.0
R2(config-if)#no shutdown

R2(config-if)#exit
R2(config)#interface gigabitethernet0/0/0
R2(config-if)#ip address 10.2.2.1 255.255.255.0
R2(config-if)#no shutdown

R2(config-if)#exit
R2(config)#router ospf 1
R2(config-router)#router-id 3.3.3.3
R2(config-router)#network 20.1.1.0 0.0.0.255 area 0
R2(config-router)#network 10.2.2.0 0.0.0.255 area 0
R2(config-router)#exit
R2(config)#end
R2#write memory
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up

%LINK-5-CHANGED: Interface GigabitEthernet0/0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0/0, changed state to up

%SYS-5-CONFIG_I: Configured from console by console

Building configuration...
[OK]
R2#
```

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R1
R1(config)#interface serial0/1/0
R1(config-if)#ip address 100.1.1.2 255.255.255.0
R1(config-if)#no shutdown

R1(config-if)#exit
R1(config)#interface gigabitethernet0/0/0
R1(config-if)#ip address 172.16.2.1 255.255.0.0
R1(config-if)#no shutdown

R1(config-if)#exit
R1(config)#router ospf 1
R1(config-router)#router-id 2.2.2.2
R1(config-router)#network 100.1.1.0 0.0.0.255 area 0
R1(config-router)#network 172.16.0.0 0.0.255.255 area 0
R1(config-router)#exit
R1(config)#end
R1#write memory
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up

%LINK-5-CHANGED: Interface GigabitEthernet0/0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0/0, changed state to up

%SYS-5-CONFIG_I: Configured from console by console

Building configuration...
[OK]
R1#
```

Copy

Paste

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname R0
R0(config)#interface serial0/1/0
R0(config-if)#ip address 100.1.1.1 255.255.255.0
R0(config-if)#clock rate 64000
R0(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
R0(config-if)#exit
R0(config)#interface serial0/1/1
R0(config-if)#ip address 20.1.1.1 255.255.255.0
R0(config-if)#clock rate 64000
R0(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/1, changed state to down
R0(config-if)#exit
R0(config)#router ospf 1
R0(config-router)#router-id 1.1.1.1
R0(config-router)#network 100.1.1.0 0.0.0.255 area 0
R0(config-router)#network 20.1.1.0 0.0.0.255 area 0
R0(config-router)#exit
R0(config)#end
R0#write memory
%SYS-5-CONFIG_I: Configured from console by console

Building configuration...
[OK]
```