```
#---------------------------------------------------------------------------
# SADMIN - Configuration file v4.0.2
#
#   - Comment line MUST begin with an # in column 1.
#   - Blank lines are ignored.
#   - The format is simple (NAME = VALUE).
#   - These are the defaults values used by sadmin tools.
#   - Most fields can be overridden on a script basis
#       Some fields like SADM_ALERT_TYPE, SADM_MAIL_ADDR can be overridden
#       in the SADMIN section at the top of script.
#       See template 'sadm_template.sh' & 'sadm_template.py' as an example.
#   - If this file 'sadmin.cfg' is not present when a script is executed,
#     then template file '.sadmin.cfg' will be copied to 'sadmin.cfg'.
#   - If both file 'sadmin.cfg' and '.sadmin.cfg' are not present, then
#     default values are used.
#
# Change Log
# 2020_05_17 config v2.3 Update Rear Backup and backup default Location,
# 2021_05_13 config v2.4 Description revisited when doing documentation.
# 2021_08_17 config v2.5 Add 'SADM_MONITOR_UPDATE_INTERVAL' var.
# 2021_08_16 config v2.6 Monitor page refresh rate 'SADM_MONITOR_UPDATE_INTERVAL'
# 2021_11_06 config v2.7 SMTP Parameters added to configuration file & setup script.
# 2023_01_05 config v2.8 Add 'SADM_BACKUP_DIF' % variable.
# 2023_10_12 config v2.9 Update all fields definitions.
#@2024_03_20 config v3.0 Add parameters for the VirtualBox tools.
#@2024_03_21 config v3.1 Revise and change some comments of each fields.
#@2025_01_30 config v3.4 Add NFS mount version for daily backup, VM export and ReaR backup.
#@2026_03_03 config v3.5 Added O/S update setting, new constant: 'SADM_VM_EXPORT_SCRIPT'
#@2026_03_03 config v3.5 New constant: 'SADM_OSUPDATE_SCRIPT' ,, 'SADM_REAR_BACKUP_SCRIPT'
#@2026_03_30 config v3.6 Add O/S update options: SADM_OSUPDATE_REBOOT_NEEDED
#@2026_03_30 config v3.6 Add O/S update options: SADM_OSUPDATE_LOCK SADM_OSUPDATE_REBOOT_TIME
#@2026_04_03 config v3.7 Add O/S update options: SADM_OSUPDATE_AUTOREMOVE, SADM_OSUPDATE_FLATPAK,
#@2026_04_03 config v3.7 Add O/S update options: SADM_OSUPDATE_SNAP
#@2026_05_09 config v3.8 Add variables for executing backup,export,ReaR backup in batch mode.
#@2026_05_20 config v3.8.2 Add variables for concurrent backup & O/S update in batch mode.
#@2026_10_01 config V4.01 Remove variable 'SADM_ALERT_REPEAT' to sadmin.cfg, by SADM_ALERT_TTL.
#@2026_10_01 config V4.02 Add variable 'SADM_ALERT_TTL' to sadmin.cfg, Sec. (86400) alert stay valid
#---------------------------------------------------------------------------


#---------------------------------------------------------------------------
# SADM_CFG_VERSION
#   - Indicate the release version of this file.
#   - PLEASE DO NOT CHANGE THIS VALUE, it is used by the SADMIN update script
```

```
43  #     to determine if this configuration file is up to date or not.
44  #   - It will be updated automatically by the SADMIN update script when a new
45  #     version is available.
46  #
47  #---------------------------------------------------------------------------
48  SADM_CFG_VERSION = 4.02



49  #---------------------------------------------------------------------------
50  # SADM_HOST_TYPE:
51  #   - Indicate whether this host is a SADMIN [S]erver or a [C]lient.
52  #   - Used in various script to activate/deactivate some feature/operation.
53  #   - Set this field accordingly, there can be only one SADMIN Server.
54  #   - Valid value are : 'S' or 'C'
55  #---------------------------------------------------------------------------
56  SADM_HOST_TYPE = C



57  #---------------------------------------------------------------------------
58  # SADM_CIE_NAME:
59  #   - Indicate your company name (site name) that appear in the heading
60  #     of the web site, some report and email that SADMIN produce.
61  #---------------------------------------------------------------------------
62  SADM_CIE_NAME = The Batcave



63  #---------------------------------------------------------------------------
64  # SADM_MAIL_ADDR:
65  #   - Specify email address used by SADMIN Tools to send various email.
66  #     For example, you can request that the log of a script to be sent when
67  #     an error occurred or every time is it run.
68  #     (See 'SADM_ALERT_TYPE' in SADMIN section at the top of your script).
69  #   - Multiple email can be specify (Comma must separate each of them).
70  #---------------------------------------------------------------------------
71  SADM_MAIL_ADDR = 20sadm22@gmail.com



72  #---------------------------------------------------------------------------
73  # Here you specify your smtp server name, port and user on the internet.
```

```
74  #
75  # If you are using gmail, modify the setting below.
76  # You need to define a secure application password, for more info visit
77  # this page (https://support.google.com/accounts/answer/185833#app-passwords)
78  #
79  # As of 30 may 2022, Google no longer accept connection from less
80  # secure application (https://support.mozilla.org/gu-IN/questions/1369886).
81  #
82  # SADMIN 'setup' script will configure for you the 'postfix' configuration
83  # file (/etc/postfix/main.cf) and the passwords files (sasl_passwd and
84  # sasl_passwd.db) in /etc/postfix.
85  #---------------------------------------------------------------------------
86  SADM_SMTP_SERVER = smtp.gmail.com
87  SADM_SMTP_PORT   = 587
88  SADM_SMTP_SENDER = 20sadm22@gmail.com



89  #---------------------------------------------------------------------------
90  # Default option for sending alert (notification) after a SCRIPT terminate.
91  # This default, can be overridden by changing 'SADM_ALERT_TYPE' in the
92  # 'SADMIN code section' at the top of your script.
93  #   0 = Don't send any alert when script terminate.
94  #   1 = Send alert only if script terminate with error.
95  #   2 = Send alert only if script terminate with success.
96  #   3 = Always send notification with status when script terminate.
97  #---------------------------------------------------------------------------
98  SADM_ALERT_TYPE = 1



99  #---------------------------------------------------------------------------
100 # Default Alert Group is 'default' (As defined in $SADMIN/cfg/alert_group.cfg)
101 # Group specified here, MUST exist in the $SADMIN/cfg/alert_group.cfg.
102 #
103 # Use in Script:
104 #  - The Default Alert Group is use to send alert within your script.
105 #  - This default can be overridden by changing 'SADM_ALERT_GROUP' in your
106 #    shell script or 'sa.sadm_alert_group' in your python script.
107 #
108 # Use by System Monitor:
109 #   When the System Monitor detect something that it could monitor (Like a
110 #   new filesystem), a new monitoring line is added with this Alert group.
111 #   Default can be overridden by changing the Warning Alert Group (Column J)
```

```
#   and the Error Alert Group (Column K), in the System Monitor configuration
#   file of the system ($SADMIN/cfg/`hostname -s`.smon).
#---------------------------------------------------------------------------
SADM_ALERT_GROUP   = default
SADM_WARNING_GROUP = default
SADM_INFO_GROUP    = default



#---------------------------------------------------------------------------
# SADMIN NTFY Paramters (https://ntfy.sh) - Not Used Yet
#---------------------------------------------------------------------------
SADM_NTFY_EMAIL     = 20sadm22@gmail.com
SADM_NTFY_USER      = 20sadm22@gmail.com
SADM_NTFY_PWD       = 5ne46yJFqmQS24rU8e9
SADM_NTFY_TOKEN     = tk_2a511lu2o46k5hdg1t64h5u55wt0
SADM_NTFY_TOPIC     = sadmdev
SADM_NTFY_URL       = https://ntfy.sh



#---------------------------------------------------------------------------
# TEXTBELT SMS TEXT MESSAGE VARIABLE
#   SADM_TEXTBELT_KEY :
#       This is the key generated by TextBelt and URL to use the SMS Service
#       Go to https://textbelt.com/ and press the 'Generate my key' button.
#       Enter your email address and decide what is the right plan for you.
#       It's $10 for 250 Text Messages, $20 for 600, $40 for 1200.
#   SADM_TEXTBELT_URL :
#       The URL to send send the SMS message.
#---------------------------------------------------------------------------
SADM_TEXTBELT_KEY = 967e5a9315cd22dddd8ffakeb645ab0a855900f042NFZPGjack1JnCr35UWzO8tIB
SADM_TEXTBELT_URL = https://textbelt.com/text



#---------------------------------------------------------------------------
# The 'SADM_ALERT_TTL' represent the number of seconds you want an alert to
# be valid. After that the alert will be ignored.
# 86400 seconds = 24 hours, 72800 seconds = 48 hours, 43200 = 12 Hours,
# 21600 seconds = 6 hours,  10800 seconds = 3 hours, 3600 seconds = 1 hour.
#
```

```
# When an alert was issued more than SADM_ALERT_TTL seconds ago, it will
# be ignore.
#
#---------------------------------------------------------------------------
SADM_ALERT_TTL = 86400



#---------------------------------------------------------------------------
# Number of days to keep an alert in the History File ($SADM_ALERT_HIST).
# When alert become older the 'SADM_DAYS_HISTORY' they are moved to the alert
# archive file ($SADM_ALERT_ARC).
# (Default 7 days)
#---------------------------------------------------------------------------
SADM_DAYS_HISTORY = 7


#---------------------------------------------------------------------------
# Maximum of lines to keep in the alert archive file ($SADM_ALERT_ARC).
# Default is 1000 lines
#---------------------------------------------------------------------------
SADM_MAX_ARC_LINE = 1000



#---------------------------------------------------------------------------
# SADM_SERVER:
#   - SADMIN server hostname - MUST be the FQDN (fully qualified domain name).
#   - This name can be an alias in the DNS.
#   - It's usually the result of the 'hostname' command on the SADMIN server.
#---------------------------------------------------------------------------
SADM_SERVER = sherlock.maison.ca



#---------------------------------------------------------------------------
# SADM_SSH_PORT:
#   - Default SSH port number (22) to communicate with the client.
#   - Can be change on a system maintenance page of each client.
#---------------------------------------------------------------------------
SADM_SSH_PORT = 32
```

```
175  #---------------------------------------------------------------------------
176  # Default domain name use when new system are added to SADMIN Tools.
177  #---------------------------------------------------------------------------
178  SADM_DOMAIN = maison.ca



179  #---------------------------------------------------------------------------
180  # Define user and group that have access to SADMIN directory ($SADMIN).
181  # The scripts Â´sadm_housekeeping_client.sh' and 'sadm_housekeeping_server.sh'
182  # will use these values to make sure all files and directories belong to them.
183  # Both of them are executed daily from the crontab '/etc/cron.d/sadm_client'
184  # and '/etc/cron.d/sadm_server' (on the SADMIN server).
185  #
186  # SADM_PWD_RANDOM: If set to 'Y' and the SADM_USER password expire, it will automatically set a
187  #                  random password to SADM_USER, and change some of the 'SADM_USER' user setting :
188  #                  'chage -m 5 -M 30 -W 10 -E -1 -I -1 $SADM_USER'.
189  #                  You should use ssh-key authentication, so you don't need to know password.
190  #                  To unlock user, 5 days before change again, password is valid for 30 days,
191  #                  Warn 10 days before expire, set account expire and password inactive to 'never'.
192  #                  If set to 'N' then if the password expire or the account lock, an error
193  #                  will be reported by sadm_housekeeping_client.sh' script.
194  #---------------------------------------------------------------------------
195  SADM_USER  = sadmin
196  SADM_GROUP = sadmin
197  SADM_PWD_RANDOM = Y



198  #---------------------------------------------------------------------------
199  # User name and group that run the apache server.
200  # Do a 'ps -ef | grep -Ei "httpd|apacahe2"' & look at the name in column one.
201  # They should be set to the user and group that is running the http server.
202  # On RedHat/CentOS/Fedora/Rocky/Alma  it is usually apache:apache
203  # On Ubuntu/Debian/Raspbian,LinuxMint it is usually www-data:www-data
204  #
205  # The daily script 'sadm_housekeeping_server.sh' will use them to make sure
206  # all files and directories '$SADMIN/www' belong to them.
207  #---------------------------------------------------------------------------
208  SADM_WWW_USER  = apache
209  SADM_WWW_GROUP = apache



210  #---------------------------------------------------------------------------
```

```
211  # MariaDB/Mysql Database Parameters
212  #---------------------------------------------------------------------------
213  SADM_DBNAME     = sadmin
214  SADM_DBHOST     = localhost
215  SADM_DBPORT     = 3306
216  SADM_RW_DBUSER  = sadmin
217  SADM_RO_DBUSER  = squery



218  #---------------------------------------------------------------------------
219  # SADM_MAX_LOGLINE:
220  #  - Indicate the maximum number of lines that each log can have.
221  #  - The default value is 500 lines, unless you change the content of
222  #    variable '$SADM_MAX_LOGLINE' (Shell Script) or 'sa.max_logline' (Python).
223  #  - Log are automatically trimmed to this number at the end of the script.
224  #  - The Log filename is  "[HOSTNAME]_sadm_[NAME_OF_SCRIPT].log"
225  #  - Logs are created or appended in ${SADMIN}/log directory depending of the
226  #    variable 'SADM_LOG_APPEND' (Y=AppendLog, N=CreateNewLog) in your bash
227  #    script or 'sa.log_append' in your Python script (Append=True or False to
228  #    create a new one).
229  #---------------------------------------------------------------------------
230  SADM_MAX_LOGLINE = 500



231  #---------------------------------------------------------------------------
232  # SADM_MAX_RCHLINE:
233  #  - Indicate the maximum number of lines that '.rch' file can have.
234  #  - RCH file are automatically trimmed to this number when script end.
235  #  - The '.rch'files reside in '${SADMIN}/dat/rch' directory.
236  #  - The '.rch' filename is "[HOSTNAME]_[NAME_OF_SCRIPT].rch".
237  #  - If you don't want to use or update the '.rch' file one of your script,
238  #    you need to specify it, by changing the value the variable
239  #    "SADM_USE_RCH='N'" (Shell Script) or 'sa.use_rch = False' (Python).
240  #
241  #  - The default value is 30 lines, unless you change the content of variable
242  #    '$SADM_MAX_RCHLINE' (Shell Script) or 'sa.cfg_max_rchline' (Python).
243  #---------------------------------------------------------------------------
244  SADM_MAX_RCHLINE = 40
```

```
245 #---------------------------------------------------------------------------
246 # SADM_NMON_KEEPDAYS:
247 # - Indicate the number of days you want to keep a 'nmon' file on each
248 #   client in '$SADMIN/dat/nmon' directory.
249 #
250 # - The script 'sadm_housekeeping_client.sh' is run daily and remove any
251 #   '*.nmon' files older than the number of day specified.
252 #
253 # - NMON file is an ASCII file created by the 'nmon' program that store system
254 #   performance data. One NMON file is produced daily on each system.
255 #       - NMON file are recorded in the '$SADMIN/dat/nmon' directory.
256 #       - The name of each 'nmon' file is "[HOSTNAME]_[yymmdd]_[hhmm].nmon"
257 #       - The home page of 'nmon' is https://nmon.sourceforge.net/pmwiki.php
258 #       - SADMIN setup script will install 'nmon' if it's not present on your
259 #         system, it's usually included in the distribution repository.
260 #
261 # Once a day the 'nmon' directory ($SADMIN/dat/nmon) of each clients is sync
262 # (rsync) to the SADMIN server in "$SADMIN/www/dat/$HOSTNAME/nmon" by the
263 # script 'sadm_server_sunrise.sh' (https://sadmin.ca/sadm-server-sunrise).
264 # It's run early in the morning via the cron (etc/cron.d/sadm_server).
265 # Every day at midnight the current nmon file is closed and a new one created.
266 #
267 # - Default value of 10 days, is a reasonable default (each file is ~1MB).
268 #---------------------------------------------------------------------------
269 SADM_NMON_KEEPDAYS = 10



270 #---------------------------------------------------------------------------
271 # The 'SADM_RCH_KEEPDAYS' field, indicated the number of days we wait, until
272 # we remove a '.rch' file that was not modified for more than the number of
273 # days specified.
274 #
275 #   - The '.rch' files are located in ${SADMIN}/dat/rch directory.
276 #   - We don't want an unused or outdated '.rch' file to stay there for ever.
277 #   - If an '.rch' file isn't updated for a long time, this may indicate
278 #     that the associated script is not used anymore or as not been run
279 #     for a while.
280 #   - It's the "sadm_client_housekeeping.sh" script that is responsible to
281 #     remove the any '.rch' file, if necessary.
282 #     It's part of the "${SADMIN}/bin/sadm_client_sunset.sh" and is
283 #     executed from the '/etc/cron.d/sadm_client' crontab every night.
284 #
285 #   - Recommended value is 35 days.
```

```
#   - A value of zero, means you don't want to delete any of the '.rch' file.
#---------------------------------------------------------------------------
SADM_RCH_KEEPDAYS = 40



#---------------------------------------------------------------------------
# SADM_LOG_KEEPDAYS:
#   - Indicate the number of days we wait until we remove a '.log' file that
#     was not modified for the number of days specified.
#
# If an LOG is not updated for a long time, this may indicate that the
# associated script don't exist anymore or have not been run for a while.
# If we don't do anything, the '.log' file will may stay there forever.
#
#   - The '.log' files are located in '${SADMIN}/log' directory.
#   - The '.log' files are updated every time the associate script is run.
#   - It's the "sadm_client_housekeeping.sh" that is responsible to remove the
#     logs if necessary. It's part of the '${SADMIN}/bin/sadm_client_sunset.sh'
#     that is executed from the '/etc/cron.d/sadm_client' crontab every night.
#
#   - Recommended value is 35 days.
#   - A value of zero, means you don't want to delete any of the old logs.
#---------------------------------------------------------------------------
SADM_LOG_KEEPDAYS = 40


#---------------------------------------------------------------------------
# If you want to received or not an email each time a system is shutdown
# and/or at system startup.
# Default value is 'Y'
#
# For this option to work the 'sadmin.service' MUST to be enable and started.
#   - 'systemctl enable --now sadmin.service'.
# The scripts 'sadm_startup.sh' and 'sadm_shutdown.sh' (in $SADMIN/sys) are
# the one that will send the email.
#
# Let's say you want to receive these emails on all systems, but not on all of them.
# You leave the default value below to 'Y' and on the system you don't want an email,
# create a file name 'sadm_startup_noemail.txt' and/or 'sadm_shutdown_noemail.txt'
# in the $SADMIN/sys directory.
#
#---------------------------------------------------------------------------
SADM_EMAIL_STARTUP  = Y
```

```
325  SADM_EMAIL_SHUTDOWN = Y



326  #---------------------------------------------------------------------------
327  # REAR BACKUP OPTIONS
328  #
329  # SADM_REAR_NFS_SERVER:
330  #   NFS server name where the ReaR backup are stored.

331  # SADM_REAR_NFS_SERVER_VER:
332  #   NFS version (3 or 4) to use to mount ReaR backup mount point (default 3).

333  # SADM_REAR_NFS_MOUNT_POINT:
334  #   NFS mount point where the ReaR backup are stored on the NFS Server.

335  # SADM_REAR_BACKUP_TO_KEEP:
336  #   Number of ReaR backup to keep at all time (Default is 3).

337  # SADM_REAR_BACKUP_DIF:
338  #   To catch your attention, when ReaR backup size differ than the previous
339  #   backup by more than 25% (for example) it will be hightlighted on the
340  #   'ReaR Backup Status' web page. Default is 25 (25%).

341  # SADM_REAR_BACKUP_INTERVAL:
342  #   To catch your attention, if a ReaR backup is older than the number of
343  #   days specify below, it will be hightlighted on the 'ReaR Backup Status'
344  #   web page (Default is 10 days).


345  # USE IN FUTUR VERSION.

346  # SADM_REAR_DEL_FAILED_BACKUP (Default = 'Y'):
347  #   When the REAR backup file (tgz), fail one of the integrity check, the
348  #   backup files are deleted from the destination directory. We don't want to
349  #   keep backup that you would have problem to restore.
350  #   If don't want to remove the backup in error, then set this field to 'N'.

351  # SADM_REAR_BATCH_MODE (Default=N) USE IN FUTUR VERSION.
352  #   - If 'Y', the rear backup will run one after another based on the
353  #     'backup sequence number' assigned to each system.
354  #   - If no rear backup sequence number' (0) is assigned to the system,
355  #     the backup will executed based on the system name in alphabetic order.
```

```
356  # SADM_REAR_BATCH_START_TIME (Default 00:00) USE IN FUTUR VERSION.
357  #   - If the ReaR back up batch mode is activated (SADM_BACKUP_BATCH_MODE=Y)
358  #     The backup will create a list of the active systems to backup sorted
359  #     by the 'backup sequence number' and system name.
360  #   - The batch backup will begin at the time specified.
361  #
362  #---------------------------------------------------------------------------
363  SADM_REAR_NFS_SERVER            = lestrade.maison.ca
364  SADM_REAR_NFS_SERVER_VER        = 3
365  SADM_REAR_NFS_MOUNT_POINT       = /backup/backup_rear
366  SADM_REAR_BACKUP_TO_KEEP        = 2
367  SADM_REAR_BACKUP_DIF            = 25
368  SADM_REAR_BACKUP_INTERVAL       = 14
369  SADM_REAR_BACKUP_SCRIPT         = sadm_rear_backup.sh
370  SADM_REAR_DEL_FAILED_BACKUP     = Y
371  SADM_REAR_BATCH_MODE            = N
372  SADM_REAR_BATCH_STARTUP_TIME    = 00:10
373  SADM_REAR_CONCURRENT            = 1
374  SADM_REAR_BATCH_DAY2RUN         = "2,7"
375  SADM_REAR_BATCH_MTH2RUN         = "0"
376  SADM_REAR_BATCH_DATE2RUN        = "0"


377  #---------------------------------------------------------------------------
378  # Daily Backup Options
379  #---------------------------------------------------------------------------
380  # SADM_BACKUP_NFS_SERVER:
381  #   NFS server name where the backup are stored.
382  # SADM_BACKUP_NFS_SERVER_VER:
383  #   NFS version (3 or 4) to use to mount backup mount point (default 3).
384  # SADM_BACKUP_NFS_MOUNT_POINT:
385  #   NFS mount point where the backup are stored on the NFS Server.
386  # SADM_DAILY_BACKUP_TO_KEEP:
387  #   Number of daily backup to keep on the NFS server.
388  # SADM_WEEKLY_BACKUP_TO_KEEP:
389  #   Number of weekly backup to keep at all time.
390  # SADM_MONTHLY_BACKUP_TO_KEEP:
391  #   Number of monthly backup to keep at all time.
392  # SADM_YEARLY_BACKUP_TO_KEEP:
393  #   Number of yearly backup to keep on the NFS server.
394  # SADM_WEEKLY_BACKUP_DAY:
395  #   - Define the day of the week to do a weekly backup (Default is 5=Friday).
396  #     1=Mon, 2=Tue, 3=Wed, 4=Thu, 5=Fri, 6=Sat, 7=Sun
```

```
# SADM_MONTHLY_BACKUP_DATE:
#   - Define the date of the month to do a Monthly Backup.
#   - So should be between the 1st and the 28th.
#   - Default is 1 for the first day of each month.
# SADM_YEARLY_BACKUP_MONTH: & SADM_YEARLY_BACKUP_DATE:
#   - Define the month (1-12) and date when to do a yearly backup (1-28)
#   - Default is the 31 december of each year.
# SADM_BACKUP_DIF:
#   - If the size of the backup is different than the previous  backup by
#     more or less than the percentage below (example 50 for 50%),
#     it will be highlighted on the 'Daily Backup Status' web page.
#   - Default is 40 for 40% (0 = Disable check)
# SADM_BACKUP_INTERVAL: (Default is 7 days)
#   - If the last backup date is older than the number of days specify
#     below it will hightlighted on the Daily Backup Status web page.
#

# USE IN FUTUR VERSION.
# SADM_BACKUP_BATCH_MODE (Default=N) USE IN FUTUR VERSION.
#   - 'Y'   It will run the backup one after another based on the
#           'sequence number' assigned to each system (On schedule web page)
#   - 'N'   The Operating System will run at the specified time on the
#           schedule web page.
#   If no 'sequence number' (0=Default) on the system backup schedule
#   web page, then the backup will execute based on the system name.
#
# SADM_BACKUP_BATCH_START_TIME (Default 00:00) USE IN FUTUR VERSION.
#   - If the backup batch mode is activated (SADM_BACKUP_BATCH_MODE=Y)
#     The backup will create a list of systems to backup sorted by the
#     'backup sequence number' and system name.
#   - The batch backup will begin at the time specified.
#   - System having is backup block enable on the schedule web page are ignored.
#
# SADM_BACKUP_BATCH_CONCURRENT = 1 (Default 1) USE IN FUTUR VERSION.
#   - Determine how many backup can run simultaniously
#   - Default is 1, so backup are done in sequence one after the other.
#   - If you have a powerful server and a fast network, you can increase this
#     number to run more backup at the same time.
#
# The script that execute the daily backup is "sadm_backup.sh".
# See https://sadmin.ca/sadm-backup for more information.
#---------------------------------------------------------------------------
SADM_BACKUP_SCRIPT              =   sadm_backup.sh
SADM_BACKUP_NFS_SERVER          =   batnas.maison.ca
```

```
SADM_BACKUP_NFS_SERVER_VER      =   3
SADM_BACKUP_NFS_MOUNT_POINT     =   /volume1/backup/backup_sadmin
SADM_DAILY_BACKUP_TO_KEEP       =   3
SADM_WEEKLY_BACKUP_TO_KEEP      =   2
SADM_MONTHLY_BACKUP_TO_KEEP     =   2
SADM_YEARLY_BACKUP_TO_KEEP      =   1
SADM_WEEKLY_BACKUP_DAY          =   5
SADM_MONTHLY_BACKUP_DATE        =   1
SADM_YEARLY_BACKUP_MONTH        =   12
SADM_YEARLY_BACKUP_DATE         =   31
SADM_BACKUP_DIF                 =   40
SADM_BACKUP_INTERVAL            =   1
SADM_BACKUP_DAY2RUN             =   "1,4,7"   # 0=NoBackup,1=Sun,2=Mon,3=Tue,4=Wed,5=Thu,6=Fri,7=Sat,8=AllDays
SADM_BACKUP_BATCH_MODE          =   N
SADM_BACKUP_BATCH_START_TIME    =   "00:05"
SADM_BACKUP_BATCH_CONCURRENT    =   1
SADM_BACKUP_BATCH_DAY2RUN       =   "2,7"
SADM_BACKUP_BATCH_MTH2RUN       =   "0"
SADM_BACKUP_BATCH_DATE2RUN      =   "0"
SADM_BACKUP_FILE_CHANGE_ERROR   =   Y
```

```
# O/S Update setting
#
# SADM_OSUPDATE_INTERVAL :
#   If the date of the last o/s update is greater than this number of days,
#   it will be highlighted on the webpage.
#   The default is 15 days.
# SADM_OSUPDATE_SCRIPT :
#   This the name of the script that will perform the Operating System update.
# SADM_OSUPDATE_AUTOREMOVE :
#   Remove package not use and not require by any other package.
#   Default = N
# SADM_OSUPDATE_FLATPAK :
#   Do you want to update the 'flatpak' package (if any) as part of the update.
#   Default = N
# SADM_OSUPDATE_SNAP (Y/N) :
#   Do you want to update the 'snap' package (if any) as part of the update.
#   Default = N
# SADM_OSUPDATE_REBOOT_NEEDED (Y/N):
#   Do you want to reboot the system after the update  (Default = N).
```

```
479 #   Everidden by value of 'Reboot after O/S update' field in the given schedule.
480 # SADM_OSUPDATE_REBOOT_TIME (Default 240) seconds:
481 #   Seconds given to start the O/S and to bring any services or applications up.
482 #   This is used when 'SADM_OSUPDATE_REBOOT_NEEDED' is set to 'Y'.
483 # SADM_OSUPDATE_LOCK (Y/N Default Y):
484 #   When 'Y' the system is locked during the O/S update. It means that no
485 #   other SADMIN script can be executed during the O/S update. It's unlock
486 #   when the O/S update is completed.
487 #   When 'N' the system stay unlock and other SADMIN process contnue as usual.

488 # NOT USED - FOR FUTURE VERSION
489 #
490 # SADM_OSUPDATE_BATCH_MODE (Default=N) USE IN FUTUR VERSION.
491 #   - 'Y' The update of the Operating System, will run in batch mode.
492 #         meaning they will be updated one after another in sequence, based
493 #         on the 'sequence number' and the 'system name', on the schedule page.
494 #         The 'sequence number' and 'system name' determine the order in whitch
495 #         the update is done.
496 #         If no update 'sequence number' (=0) the O/S update execute based on
497 #         the system name in alphabetic order.
498 #   - 'N' The Operating System will run at the time you specify in the
499 #         normal schedule web page.
500 #
501 # SADM_OSUPDATE_BATCH_START_TIME (Default 00:00) USE IN FUTUR VERSION.
502 #   - If the O/S Update batch mode is activated (SADM_OSUPDATE_BATCH_MODE=Y),
503 #     the update script will create a list of the active systems to update sorted
504 #     by the 'backup sequence number' and 'system name'.
505 #   - The batch backup will begin at the time specified.
506 #   - This field is not considered in "SADM_OSUPDATE_BATCH_MODE" if anything
507 #     but 'Y' is specified.
508 #
509 # SADM_OSUPDATE_BATCH_CONCURRENT (Default 1) USE IN FUTUR VERSION.
510 #   - How many systems do you want to update concurently (Default is 1).
511 #---------------------------------------------------------------------------
512 SADM_OSUPDATE_INTERVAL          =   15
513 SADM_OSUPDATE_SCRIPT            =   sadm_osupdate.sh
514 SADM_OSUPDATE_AUTOREMOVE        =   N
515 SADM_OSUPDATE_FLATPAK           =   Y
516 SADM_OSUPDATE_SNAP              =   N
517 SADM_OSUPDATE_REBOOT_NEEDED     =   N
518 SADM_OSUPDATE_REBOOT_TIME       =   240
519 SADM_OSUPDATE_LOCK              =   Y
520 SADM_OSUPDATE_BATCH_MODE        =   N
521 SADM_OSUPDATE_BATCH_START_TIME  =   "00:05"
```

```
SADM_OSUPDATE_CONCURRENT        =   1
SADM_OSUPDATE_BATCH_DAY2RUN     =   "2,7"
SADM_OSUPDATE_BATCH_MTH2RUN     =   "0"
SADM_OSUPDATE_BATCH_DATE2RUN    =   "0"



#---------------------------------------------------------------------------
# Subnet to scan, to feed the 'Information about subnet...' web page.
#---------------------------------------------------------------------------
# SADM_NETWORK[1-5]:
#   - Specify the network subnet you want to scan daily.
#   - Results can be viewed by clicking on "Network" in the heading of the
#     web interface.
# For more information visit https://sadmin.ca/sadm-subnet-lookup
#---------------------------------------------------------------------------
SADM_NETWORK1 = 192.168.1.0/24
SADM_NETWORK2 =
SADM_NETWORK3 =
SADM_NETWORK4 =
SADM_NETWORK5 =



#---------------------------------------------------------------------------
# Systems Monitor Status Web Page Parameters Section
#---------------------------------------------------------------------------
# SADM_MONITOR_UPDATE_INTERVAL:
#   - The number of seconds the SADMIN Monitor Web Page is refresh.
#   - Default is 60 seconds, so the monitor page will refresh every 60 sec.
# SADM_MONITOR_RECENT_COUNT:
#   - The number of recent scripts to appears on the SADMIN Monitor page.
#   - If set to 0, recent scripts section won't appear on the monitor page.
#   - Default is 10.
# SADM_MONITOR_RECENT_EXCLUDE:
#   - Specify script name to exclude from recent scripts execution list
#     on the SADMIN Monitor Web page & on the command line command
#     'srch' (link to sadm_show_rch.sh) script output.
#   - Each script name (without extension) must be separated by a comma.
#   - Default entries: sadm_nmon_watcher,sadm_fetch_clients
#---------------------------------------------------------------------------
SADM_MONITOR_UPDATE_INTERVAL = 60
SADM_MONITOR_RECENT_COUNT    = 5
```

```
559  SADM_MONITOR_RECENT_EXCLUDE  = sadm_nmon_watcher,sysmon_script_test



560  #---------------------------------------------------------------------------
561  # SADM_PID_TIMEOUT:
562  #   - Specify the maximum number of seconds that a PID file can prevent the
563  #     script from executing.
564  #   - Every time a script start it created a PID file.
565  #   - PID file name is "${SADMIN}/tmp/SCRIPT_NAME.pid".
566  #
567  #   - If a PID file exist when a script start, it check the creation time
568  #     of the pid file. If the number of seconds elapsed since it was created
569  #     is more than the value below, the PID file is deleted, recreated,
570  #     and the script execute normally.
571  #   - So if a script abort and the PID file isn't remove, the script will
572  #     never run again, unless 'SADM_MULTIPLE_EXEC="Y"' (Shell Script) or
573  #     'sa.multiple_exec="Y"' (Python) was set or PID file remove manually,
574  #     or this timeout is exceeded.
575  #.
576  #   - Default is 14400, (4hrs) but can modified on a script basis by changing
577  #     the value of "$SADM_PID_TIMEOUT" (Shell script) or 'sa.pid_timeout'
578  #     (Python) in the SADMIN section.
579  #---------------------------------------------------------------------------
580  SADM_PID_TIMEOUT = 14400



581  #---------------------------------------------------------------------------
582  # SADM_LOCK_TIMEOUT:
583  #   - This parameter specify the number of seconds (3600=1hrs) that a system
584  #     can be locked. When a system is lock it is no longer monitored and the
585  #     SADMIN server won't be allowed to start any script on that system.
586  #
587  #   - A system is lock, when a file with it name is created in the $SADMIN dir.
588  #   - The system lock file is only created on the SADMIN server.
589  #   - The lock file name is '$SADMIN/$HOSTNAME.lock".
590  #
591  # When a script start on the SADMIN server and a lock file exist on the
592  # SADMIN server, it check the creation time of the lock file.
593  # If it was created more than the value below the lock file is deleted and
594  # the script executed.
595  #
596  # Value can modify on a script basis by modifying value of the field
```

```
# 'SADM_LOCK_TIMEOUT' (Script) or 'sa.lock_timeout' (Python).
# Default is 7200 (2hrs).
#---------------------------------------------------------------------------
SADM_LOCK_TIMEOUT = 7200


#---------------------------------------------------------------------------
# Virtual Box Machine Backup (OVA) Options
#---------------------------------------------------------------------------
# SADM_VM_EXPORT_NFS_SERVER:
#   NFS Server name where the Virtual Machine will be exported.
# SADM_VM_EXPORT_NFS_SERVER_VER:
#   NFS version (3 or 4) to use to mount the export mount point (default 3).
# SADM_VM_EXPORT_MOUNT_POINT:
#   NFS mount point where the export files are stored on NFS Server.
# SADM_VM_EXPORT_TO_KEEP:
#   Number of export directory per VM to keep at all time.
#   The oldest export directory is deleted when this number is exceeded.
# SADM_VM_EXPORT_INTERVAL:
#   When no 'export' is done for more than 'SADM_VM_EXPORT_INTERVAL' days,
#   the VM status page will highlight this fact with a different color.
#   (Default is 14 days).
# SADM_VM_EXPORT_ALERT:
#   Y = Issue an alert when export interval is exceeded.
#   N = Don't send an alert when export interval is exceeded (Default).
# SADM_VM_USER:
#   Username that is assigned to the 'vboxusers' user group.
# SADM_VM_STOP_TIMEOUT:
#   Seconds given to stop a VM using the acpi shutdown, before issuing a poweroff.
# SADM_VM_START_INTERVAL:
#   When you decide start all VMs, this is the number of seconds we sleep
#   before starting the next one.
# SADM_VM_EXPORT_DIF:
#   To catch your attention, when VM export size differ than the previous
#   one by more than 25% (for example) it will be hightlighted on the
#   'Export Status' web page. Default is 25 (25%).


# NOT USED - FOR FUTURE VERSION
#
# SADM_VM_EXPORT_BATCH_MODE (Default=N) USE IN FUTUR VERSION.
#   - 'Y' The creation of an export file, will run in batch mode,
#         meaning the exports will run one after another, sorted by
#         'sequence number' and 'system name'.
```

```
637  #         The 'sequence number' and 'system name' determine the order in
638  #         whitch the export is done.
639  #         If no update 'sequence number' (0) the export is based on the
640  #         system name in alphabetic order.
641  #         This variable can be change in the 'Export Schedule' of the system.
642  #   - 'N' The Operating System will run at the time you specify in the
643  #         normal schedule page..
644  #   - 'B' Block exports, no export will be done, until put back to 'Y'or 'N'.
645  #         Do this if you don't want to execute any exports of your VM
646  #
647  # SADM_VM_EXPORT_START_TIME (Default 00:00) USE IN FUTUR VERSION.
648  #   - If the export batch mode is activated (SADM_VM_EXPORT_BATCH_MODE=Y),
649  #     the export will create a list of the active systems sorted by the
650  #     'export sequence number' and 'system name'.
651  #   - The batch backup will begin at the time specified.
652  #   - This field is NOT considered if "SADM_OSUPDATE_BATCH_MODE" is anything
653  #     but 'Y'.
654  #---------------------------------------------------------------------------
655  SADM_VM_EXPORT_NFS_SERVER           = batnas.maison.ca
656  SADM_VM_EXPORT_NFS_SERVER_VER       = 3
657  SADM_VM_EXPORT_MOUNT_POINT          = /volume1/backup/backup_vm/vbox_exports
658  SADM_VM_EXPORT_TO_KEEP              = 2
659  SADM_VM_EXPORT_INTERVAL             = 21
660  SADM_VM_EXPORT_ALERT                = Y
661  SADM_VM_USER                        = jacques
662  SADM_VM_STOP_TIMEOUT                = 60
663  SADM_VM_START_INTERVAL              = 30
664  SADM_VM_EXPORT_DIF                  = 25
665  SADM_VM_EXPORT_SCRIPT               = sadm_vm_export.sh
666  SADM_VM_EXPORT_BATCH_MODE           = N
667  SADM_VM_EXPORT_BATCH_START_TIME     = "00:01"
668  SADM_VM_EXPORT_CONCURRENT           = 1
669  SADM_VM_EXPORT_BATCH_DAY2RUN        = "2,7"
670  SADM_VM_EXPORT_BATCH_MTH2RUN        = "0"
671  SADM_VM_EXPORT_BATCH_DATE2RUN       = "0"
```